



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

E-mail Server Administration Guide

JavaMail Properties

Contents

- 1 JavaMail Properties
 - 1.1 Set Internally, Not User-Modifiable
 - 1.2 Set Internally, User-Modifiable
 - 1.3 Not Set Internally, User-Modifiable

JavaMail Properties

E-mail Server uses the JavaMail API library 1.5.1. JavaMail can make use of numerous properties, which are documented at the following locations:

- Environment properties: <http://www.oracle.com/technetwork/java/javamail-1-149769.pdf> (Appendix A: Environment Properties)
- JavaMail Session properties: <https://javamail.java.net/nonav/docs/api/>
- JavaMail Session properties for IMAP: <https://javamail.java.net/nonav/docs/api/com/sun/mail/imap/package-summary.html>
- JavaMail Session properties for POP3: <https://javamail.java.net/nonav/docs/api/com/sun/mail/pop3/package-summary.html>

These properties are treated in different ways in eServices, depending on

- Whether they are set internally by E-mail Server.
- Whether they can be modified by users.

These two parameters define three different categories of property:

- Set internally and not user-modifiable
- Set internally and user-modifiable
- Not set internally and user-modifiable

The next three sections list the properties in each category and describe how to set the ones in user-modifiable categories.

Set Internally, Not User-Modifiable

- mail.pop3.class
- mail.imap.class

Set Internally, User-Modifiable

- mail.debug
- mail.pop3.host
- mail.pop3.user
- mail.pop3.port

- mail.pop3.connectiontimeout
- mail.pop3.timeout
- mail.pop3.socketFactory.class
- mail.pop3.socketFactory.fallback
- mail.pop3.socketFactory.port
- mail.pop3.socks.host
- mail.pop3.socks.port
- mail.imap.host
- mail.imap.user
- mail.imap.port
- mail.imap.connectiontimeout
- mail.imap.timeout
- mail.imap.socketFactory.class
- mail.imap.socketFactory.fallback
- mail.imap.socketFactory.port
- mail.imap.socks.host
- mail.imap.socks.port
- mail.smtp.socks.host
- mail.smtp.socks.port

You can modify these using existing configuration options in the **[pop-client]** and **[smtp-client]** sections, as shown in the following table. In this table, <protocol> is either POP3 or IMAP; for example, mail.<protocol>.timeout covers mail.pop3.timeout and mail.imap.timeout.

JavaMail Properties Controlled by Configuration Options:

JavaMail Property	Configuration Option
mail.debug	enable-debug
mail.<protocol>.connectiontimeout	connect-timeout
mail.<protocol>.timeout	protocol-timeout
mail.<protocol>.user	mailbox
mail.<protocol>.host	server
mail.<protocol>.port mail.<protocol>.socketFactory.port	port
mail.<protocol>.socketFactory.class mail.<protocol>.socketFactory.fallback	enable-ssl

See the [eServices Options Reference](#) for complete information on these options.

Not Set Internally, User-Modifiable

Any of the properties not listed in the two preceding sections can be modified by creating options in E-mail Server's `pop-client` section. The option name is the property name. For the value, see the JavaMail documentation listed above.

Important

Do not use this method to modify the properties, listed in the preceding section, that are controlled by configuration options.

Here is an example of adding an option to modify a JavaMail property: Some POP3 servers do not properly implement TOP, an optional POP command. This can create conflicts between the results of the TOP and RETR commands, which in turn can prevent E-mail Server from parsing the retrieved e-mail. To prevent these conflicts, you can create an option that invokes JavaMail's `mail.pop3.disabletop` property. The option name is `mail.pop3.disabletop`, it must be in the `pop-client` section, and its value must be `true`. E-mail Server then does not use TOP to retrieve messages, only RETR.