



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Genesys Pulse Deployment Guide

Genesys Pulse 8.5.0

Table of Contents

Pulse Deployment Guide	3
Introducing Pulse	4
Pulse Architecture and Components	20
Deploying Pulse Collector and Pulse	23
Pulse Configuration Options	34
Starting and Stopping Pulse	54
Starting and Stopping Pulse Collector	55
Application Files	61
Change History	63

Pulse Deployment Guide

Pulse is a Genesys Administrator Extension (GAX) plug-in application that enables at-a-glance views of real-time contact center statistics within the GAX graphical user interface. Pulse uses widgets to display user-defined List, Donut, Key Performance Indicator (KPI), or Grid charts of statistics for objects.

Important

This Deployment Guide provides instructions for a new installation of Pulse. To migrate from an earlier version of Pulse, start with the [Pulse 8.5 Deployment Procedure](#).

About Pulse

Find overview information about architecture, components, and other concepts for Pulse.

[Introducing Pulse](#)

[Architecture](#)

[Framework Components](#)

Deploying Pulse

Plan your environment and install deploy Pulse.

[Deploying Pulse and Pulse Collector](#)

[Configurations Options](#)

[Application Files](#)

Starting and Stopping

Start or stop the applications:

[Pulse](#)

[Pulse Collector](#)

Change History

Find information about what has changed in this release of the content.

[Change History](#)

Introducing Pulse


Genesys Pulse is a widget-driven, graphical user application, which is accessible from a web browser as a Genesys Administrator Extension (GAX) plug-in application. Using a direct communication link to a real-time metrics engine, Stat Server, Genesys Pulse enables at-a-glance views of real-time contact center statistics within the GAX user interface.

The tabs below provide a quick visual representation of some of the Pulse functionality and a list of the Genesys-provided templates. For more details, see the [Pulse User's Guide](#).


Dashboard

Pulse Dashboard Examples

1. Examples of a Sales Team Lead dashboard




User-defined Sales Team Lead dashboard




User-defined Sales Team Lead dashboard

2. Example of a Sales Service Level dashboard for Supervisor




User-defined Sales Service Level dashboard for Supervisor

- 3. Example of a multi-channel dashboard for Supervisor




User-defined multi-channel dashboard for Supervisor

4. Example of an outbound campaign dashboard for Supervisor



User-defined outbound campaign dashboard for Supervisor

5. Example of a back-office dashboard for Supervisor



User-defined back-office dashboard for Supervisor

Expanded Charts


Expanded Charts

You can expand a widget to view detailed charts: Line; Grouped Bar; Stacked Bar; and Grid. Within the expanded charts, you can use sort options, define objects, and define statistics.

1. Line Chart




Line Chart




Line Chart

2. Grouped Bar Chart



Grouped Bar Chart

3. Stacked Bar Chart



Stacked Bar Chart

4. Grid

Name	Work Items Processed	Work Items Accepted	Work Items Rejected	Work Items Terminated	Calls Processed	Calls Transferred	Work Items Transfers	Avg Processing Time
Sippola, Kristi	1	1	1	0	0	0	0	00:11:42
Chanel, Monique	3	3	1	0	0	0	0	00:36:21
Milburn, Kristen	1	1	0	0	0	0	0	00:12:26
Hammond, Steve	0	0	0	0	0	0	0	00:00:00
McDaddy, Trevor	0	0	0	0	0	0	0	00:00:00



Grid

Widgets

Widgets

On the Pulse dashboard, statistics and objects can be displayed within different type of user-defined widgets: Donut; Grid; Key Performance Indicator (KPI); and List. You can view and select additional details and options by expanding a widget to a dashboard tab.

Widget	Examples																					
<p>List Widget</p> <p>This widget displays either one statistic for many objects or many statistics for one object. Depending on the reference selected, the Headline type option might be available for this widget type.</p>	<p>CT - EWM - Distribution</p> <p>PFS System</p> <table border="1"> <tr><td>Credit Card Distr.</td><td>4</td></tr> <tr><td>Home Equity Distr.</td><td>9</td></tr> <tr><td>New Account Distr.</td><td>13</td></tr> <tr><td>Repair Distr.</td><td>13</td></tr> <tr><td>Total Disconnect</td><td>13</td></tr> </table>	Credit Card Distr.	4	Home Equity Distr.	9	New Account Distr.	13	Repair Distr.	13	Total Disconnect	13	<p>CT - EWM - Priority</p> <p>PFS System</p> <table border="1"> <tr><td>0-100</td><td>0</td></tr> <tr><td>100-200</td><td>0</td></tr> <tr><td>200-300</td><td>8</td></tr> <tr><td>300-400</td><td>0</td></tr> <tr><td>400-500</td><td>0</td></tr> </table>	0-100	0	100-200	0	200-300	8	300-400	0	400-500	0
Credit Card Distr.	4																					
Home Equity Distr.	9																					
New Account Distr.	13																					
Repair Distr.	13																					
Total Disconnect	13																					
0-100	0																					
100-200	0																					
200-300	8																					
300-400	0																					
400-500	0																					
<p>Donut Widget</p> <p>This widget displays either:</p> <ul style="list-style-type: none"> • one statistic for four specific objects • one statistic for three top objects and a sum the remaining objects • one object with the values of four defined statistics <p>Depending on the reference selected in the Cycle By option, a carousel can be defined to display additional several items.</p>	<p>Queue Activity</p> <p>Agent Group Current Status</p> <p>Calls Answered</p> <p>Bluesky</p> <table border="1"> <tr><td>A Sales_Platinum</td><td>332</td></tr> <tr><td>B Sales_Gold</td><td>199</td></tr> <tr><td>C Sales_Silver</td><td>49</td></tr> </table> <table border="1"> <tr><td>A Agents Logged In</td><td>23</td></tr> <tr><td>B Agents Not Ready</td><td>8</td></tr> <tr><td>C Agents ACW</td><td>4</td></tr> <tr><td>D Agents Waiting</td><td>15</td></tr> </table>		A Sales_Platinum	332	B Sales_Gold	199	C Sales_Silver	49	A Agents Logged In	23	B Agents Not Ready	8	C Agents ACW	4	D Agents Waiting	15						
A Sales_Platinum	332																					
B Sales_Gold	199																					
C Sales_Silver	49																					
A Agents Logged In	23																					
B Agents Not Ready	8																					
C Agents ACW	4																					
D Agents Waiting	15																					

Widget	Examples																			
	Donut Widget	Donut Widget																		
<p>KPI widget</p> <p>This widget displays either one statistic for several objects or several statistics for one object, depending on the value of the Cycle By option. The Cycle By option is available if the widget has objects selected individually, not by group.</p>	 <p>KPI Widget</p>																			
<p>Grid widget</p> <p>This widget displays a grid listing objects in rows with statistics in columns.</p>	 <p>Grid Widget</p> <table border="1" data-bbox="638 1161 1461 1612"> <thead> <tr> <th>Name</th> <th>Work Items Processed</th> <th>Calls Processed</th> </tr> </thead> <tbody> <tr> <td>Sippola, Kristi</td> <td>1 </td> <td>0</td> </tr> <tr> <td>Chanel, Monique</td> <td>3 </td> <td>0</td> </tr> <tr> <td>Milburn, Kristen</td> <td>1 </td> <td>0</td> </tr> <tr> <td>Hammond, Steve</td> <td>0 </td> <td>0</td> </tr> <tr> <td>McDaddy, Trevor</td> <td>0 </td> <td>0</td> </tr> </tbody> </table>		Name	Work Items Processed	Calls Processed	Sippola, Kristi	1	0	Chanel, Monique	3	0	Milburn, Kristen	1	0	Hammond, Steve	0	0	McDaddy, Trevor	0	0
Name	Work Items Processed	Calls Processed																		
Sippola, Kristi	1	0																		
Chanel, Monique	3	0																		
Milburn, Kristen	1	0																		
Hammond, Steve	0	0																		
McDaddy, Trevor	0	0																		

Widget	Examples																								
	<div style="text-align: right; margin-bottom: 5px;">⋮</div> <div style="border: 1px solid #ccc; padding: 5px;"> <p>Agent Login</p> <table border="1" style="width: 100%; border-collapse: collapse;"> <thead> <tr> <th style="width: 40%;">Name</th> <th style="width: 30%;">Current Status</th> <th style="width: 30%;">Login Time</th> </tr> </thead> <tbody> <tr> <td>Calfee, Marsha</td> <td> (00:00:01)</td> <td>00:09:47</td> </tr> <tr style="background-color: #e6f2ff;"> <td>Halter, Stephane</td> <td> (00:00:59)</td> <td>00:09:47</td> </tr> <tr> <td>Tamblyn, Eric</td> <td> (00:00:00)</td> <td>00:09:47</td> </tr> <tr> <td>Teresa, Teresa</td> <td> (00:00:00)</td> <td>00:09:47</td> </tr> <tr> <td>Brow, Scott</td> <td> (00:00:01)</td> <td>00:09:47</td> </tr> <tr> <td>Carlson, Brad</td> <td> (00:00:03)</td> <td>00:09:47</td> </tr> <tr> <td>Rigel, Barb</td> <td> (00:00:04)</td> <td>00:09:47</td> </tr> </tbody> </table> </div> <p style="font-size: small; margin-top: 5px;">Grid Widget</p>	Name	Current Status	Login Time	Calfee, Marsha	(00:00:01)	00:09:47	Halter, Stephane	(00:00:59)	00:09:47	Tamblyn, Eric	(00:00:00)	00:09:47	Teresa, Teresa	(00:00:00)	00:09:47	Brow, Scott	(00:00:01)	00:09:47	Carlson, Brad	(00:00:03)	00:09:47	Rigel, Barb	(00:00:04)	00:09:47
Name	Current Status	Login Time																							
Calfee, Marsha	(00:00:01)	00:09:47																							
Halter, Stephane	(00:00:59)	00:09:47																							
Tamblyn, Eric	(00:00:00)	00:09:47																							
Teresa, Teresa	(00:00:00)	00:09:47																							
Brow, Scott	(00:00:01)	00:09:47																							
Carlson, Brad	(00:00:03)	00:09:47																							
Rigel, Barb	(00:00:04)	00:09:47																							

Genesys-provided Templates

Genesys-provided Templates

The following is a list of Genesys-provided templates:

Template	Description
Agent Group Status	Presents the current number of agents in the various states.
Agent KPIs	Presents reports with KPIs of agent group in a contact center.
Agent Login	Presents an agent's properties and login information.
Campaign Activity	Monitors the activity associated with outbound campaigns.
Campaign Callback Status	A report presenting information related to

Template	Description
	campaign initiated callbacks.
Campaign Group Activity	Monitor the activity associated with outbound Campaign Groups.
Campaign Group Status	Monitor the current state and durations associated with outbound campaign group activity.
Email Agent Activity	A report presenting agent or agent group activity as it relates to the processing of Email type contacts.
Email Queue Activity	A queue report presenting an overview of current or near real-time activity in the individual email queues.
eServices Agent Activity	Monitors agent group KPIs related to eServices (chat, email, SM) media to monitor and see if behavior problems exist that need to be addressed.
eServices Queue KPIs	A queue report presenting an overview of current or near real-time activity for eServices channels.
IWD Agent Activity	A report presenting agent or agent group activity as it relates to the processing iWD work items type contacts.
IWD Queue Activity	A queue report presenting an overview of current or near real-time activity associated with the iWD queues.
Queue KPIs	Presents call activity statistics associated with the queues.
Queue Overflow Reason	Presents reasons why calls were cleared from queues.

Pulse Architecture and Components

Pulse is a Genesys Administrator Extension (GAX) plug-in application that enables at-a-glance views of real-time contact center statistics within the GAX graphical user interface. Pulse uses widgets to display user-defined List, Donut, Key Performance Indicator (KPI), or Grid charts of statistics for objects.


Using Pulse you can:

- Create widgets from predefined and user-defined templates for a fast and easy text or graphical presentation of selected or user-defined object statistics.
- Monitor the current state and activity of contact center objects to help make decisions about staffing, scheduling and call routing strategies.

Architecture

Pulse Architecture

Major aspects of Pulse are shown in the following Pulse Architecture diagram:



Pulse Collector

Pulse Collector is a background near-realtime statistical data collection and processing engine. It performs the following activities:

- Reads the metadata from the Pulse database upon startup and whenever changes are made to report definitions in Pulse.
- Uses the report definitions stored in the Pulse database to determine which statistics and objects to include.
- Creates snapshots with current data from Stat Server and formula-based statistics calculated by Pulse Collector, on the specified file system for reference by Pulse.
- Maintains a constant connection with Configuration Server to retrieve changes, additions, and deletions to configuration objects.

Pulse

Pulse is a GAX plug-in that performs the following activities:

- Handles user authentication and permissions validation.
- Filters and delivers report data according to the permissions and tenancy of the user who is requesting the data.

Displays report content in widgets, such as the listing and content of reports.

- Saves the report definitions to the Pulse Database, which it shares with Pulse Collector.

You can have only one Pulse application for each GAX instance. For configuration, Pulse requires a [pulse] section and is added to the options of the GAX Application object. Pulse must have its own database access point, but otherwise uses Management Framework and other connections from GAX.

Pulse uses the existing GAX client architecture, which is described in the [Genesys Administrator Extension Deployment Guide](#).

See the [Pulse User's Guide](#) to learn how to operate this user interface. This is also accessible from within the software, when you click help.

Framework Components

Genesys Framework Components

Pulse interacts with several products within the Genesys Framework to provide real-time snapshots of contact center data.

Configuration Server

Configuration Server provides the following data to Pulse Collector:

- Information about the existence of contact center objects (for example, tenants, agents, places, calling lists, or campaigns)
- Statistical parameters (for example, time ranges, time profiles, filters, and statistical types)
- Information about changes to contact center objects (for example, a deleted agent, a renamed queue, or a new Agent Group).

Pulse Collector uses this data to provide content for Pulse.

Both Pulse and Pulse Collector connect to Configuration Server in order to retrieve their own configuration.

Stat Server

Stat Server tracks information about customer interaction networks consisting of one or more contact centers in conjunction with one or more computer networks. Stat Server receives information from one or more T-Server or SIP Server applications and converts the accumulated data for directory numbers, agents, agent groups, and so on, into statistical information.

As a client of Stat Server, Pulse Collector requests statistics for objects belonging to particular reports. Stat Server supplies both information about the interactions that the objects that handle as well as noninteraction-related data about the objects themselves (for example, agent status). Pulse Collector returns information for all stat types that are configured in the options of all Stat Servers to which Collector is connected.

Refer to the [Stat Server User's Guide](#) and [Stat Server Deployment Guide](#) for information about Stat Server.

DB Server

DB Server is the Genesys component that handles database requests from multiple client processes. DB Server provides a single interface from the clients to a variety of database engines, including Microsoft SQL Server, Oracle and PostgreSQL. As a client of DB Server, Pulse Collector reads information about active widgets and updates the layout statuses, when layout status changes occur within the Pulse Collector.

Refer to the [\[Framework 8.1 DB Server User's Guide\]](#) for information about DB Server.

Deploying Pulse Collector and Pulse

Important

- This Deployment Guide provides instructions for a new installation of Pulse. To migrate from an earlier version of Pulse, start with the [Deployment Procedure](#).
- In these procedures, use the instructions provided in [Genesys Administrator Extension \(GAX\) Help](#) or the [Framework 8.x Deployment Guide](#), and add the object-specific configuration requirements listed here.

1. Confirm Software Requirements.

Confirm Software Requirements

You deploy Pulse as a GAX plug-in on a web application server to be accessed using a web browser through the GAX user interface. No additional Genesys software is needed on the client machine.

The following are prerequisites for Pulse deployment:

- GAX release 8.5.000.44 or higher must be installed and configured. See the [GAX Deployment Guide](#) for details.
- Tomcat is no longer a prerequisite to use GAX. For those who choose to use Tomcat instead of Jetty, refer to the [GAX Deployment Guide](#) for additional information.
- Genesys DB Server must be release 8.1.300.05 or higher. Refer to the [Framework 8.0 DB Server User's Guide](#) for details.
- Genesys Deployment Agent (GDA) must be installed on the computer on which you install Pulse and Pulse Collector if you plan to install Pulse by using GAX. GDA is required to deploy solution definitions and IPs through GAX. See the [GAX Deployment Guide](#) for details.
- Your Relational Database Management System (RDBMS) must be up and running. The 8.5 release of Pulse supports the following relational database platforms:
 - Microsoft SQL Server 2008, 2012
 - Oracle 11g, 12c
 - PostgreSQL 9.0
- The computer on which you install Pulse must be running one of the following:
 - Windows Server 2008 R2 (64-bit), 2012 (64-bit)
 - Red Hat Enterprise Linux AS 6.x (64-bit), with Updates from RHN enabled

- If you use Red Hat Enterprise Linux AS, you must also install the following libraries to ensure backward compatibility for applications: compat-db
 - compat-expat1
 - compat-glibc
 - compat-libf2c-34
 - compat-libgcc-296
 - compat-libgfortran-41
 - compat-libstdc++-295
 - compat-libstdc++-296
 - compat-libstdc++-33
 - compat-libtermcap
 - compat-openldap
 - openssl098e

For more information, see linuxtopia.org.

- If you use Windows, you must also install Microsoft Visual C++ 2010 Redistributable Package (x86 for Collector x86 and x64 for Collector x64).
- Although not required for deployment, you must have Stat Server release 8.1.2 or higher installed for basic operation.

2. Prepare the Pulse Database.

Prepare the Pulse Database

In High Availability (HA) configurations, configure both Pulse applications to use the same database.

Microsoft SQL Server

1. Create a new empty Microsoft SQL Server database.
2. Create a new Microsoft SQL Server user account.
3. Set the new database as default database for the user.
4. Grant the new user sufficient privileges for the new database. User must be able to create database objects and select, insert, update, and delete data in tables.
5. Run the statement below for the Pulse database (DB). Replace <Pulse DB> with the name of the Pulse DB and make sure that there are no other connections to the Pulse DB when you run this statement:
`ALTER DATABASE <Pulse DB> SET READ_COMMITTED_SNAPSHOT ON;`

Oracle

1. Create a new user/schema to be used by Pulse. The user must have RESOURCE and CREATE VIEW privileges.

PostgreSQL

1. Create a new empty PostgreSQL database.
2. Create a new PostgreSQL user account.
3. Set the new database as default database for the user.
4. Grant the new user sufficient privileges for the new database. User must be able to create database objects and select, insert, update, and delete data in tables.

3. Deploy Pulse Collector.

Deploying Pulse Collector

To deploy Pulse Collector, which connects directly to Stat Server to collect statistics for contact center objects. Pulse Collector also connects to DB Server, through which it accesses the database where reporting layouts are stored.

1. Upload Pulse Collector Installation Package and Template:
 - a. In GAX, go to **Administration > Installation Packages** and click on the plus sign.
 - b. Select **Installation Package Upload (template uploaded separately)** and click **Next**.
 - c. For **Upload a Package**, select the zipped file that contains the Pulse Collector Installation Package (for example, \PulseCol\version\linux\b1\ip, which has the Installation Package description file).
 - d. For **Upload an XML template**, select the XML Template file (Collector.xml from the Templates Installation Package directory).
 - e. For **Upload an APD template**, select the APD Template file (Collector.apd from Templates Installation Package directory).
 - f. Click **Finish**.
2. Deploy the Pulse Collector Installation Package and Template:
 - a. Click on the Pulse Collector Installation Package to open the Properties tab.

Important

The Pulse Collector Installation Package status should be Complete.

- b. Click on the related icon and choose **Install** to open the IP Deployment Wizard.
- c. Fill required fields and finish the installation.

Important

The InstallPath should point to an empty folder.

Tip

You can also install Pulse Collector directly on the server by executing the Pulse Collector installation procedure from the Pulse Collector installation package, then uploading the Pulse Collector template (Collector.apd) using Configuration Manager.

3. Optional: To change the default options for Pulse Collector in GAX, open the Pulse Collector Application object modify the values of configuration options described in [Pulse Collector Application Object](#).
 4. For a high-availability (HA) deployment, repeat step 2 to install the backup instance to separate folder. You need a Pulse Collector for each instance of the Pulse application.
 5. In GAX, add the Pulse Collector Application object to the connections of your GAX Application object.
 6. For a load-balanced environment configuration with two GAX applications and Pulse plug-ins, associate one GAX with the primary Pulse Collector and the second GAX with the backup Pulse Collector as follows:
 - a. Add the primary Pulse Collector Application object to the connections of the first (or primary) GAX Application object.
 7. Add the backup Pulse Collector Application object to the connections of the second (or backup) GAX Application object.
 8. Add the backup Pulse Collector Application object to the **General** tab of the primary Pulse Collector Application object as a backup server.

Note: One GAX pair can be connected to multiple Pulse Collector HA pairs. In this case, you must associate all primary Pulse Collectors with one GAX, and all the backup Pulse Collectors with the other GAX.
- Create a new Database Access Point (DAP), which is necessary for connectivity to the Pulse database through the DB Server:
 - a. Select the Default connection type.

- b. Specify Database Server Application object in **DB Server** field.
 - c. Specify the connectivity parameters for your RDBMS.
 - d. On the **Ports** tab, change the default port value to the value of your DB Server port.
- In the connections of the Pulse Collector Application, add the DAP that is to be used by Pulse Collector.
 - In the connections of the Pulse Collector Application, add the primary Stat Server application that is to be used by Pulse Collector.
 - Add the Tenant objects to the Tenants tab for all Pulse Collectors that you plan to monitor in Pulse.

4. Deploy Pulse.

Deploying Pulse

Configure the necessary objects required by Pulse using GAX.

1. Upload Pulse Installation Package and Template:
 - a. In GAX, go to **Administration > Installation Packages** and click on the plus sign.
 - b. Select **Installation Package Upload (template uploaded separately)** and click **Next**.
 - c. For **Upload a Package**, select the zipped file that contains the Pulse Installation Package (for example, \Pulse\version\linux\b1\ip, which has the Installation Package description file).
 - d. For **Upload an XML template**, select the XML Template file (Pulse.xml from the Templates Installation Package directory).
 - e. For **Upload an APD template**, select the APD Template file (Pulse.apd from Templates Installation Package directory).
 - f. Click **Finish**.
2. Deploy the Pulse Installation Package and Template:
 - a. Click on the Pulse Installation Package to open the **Properties** tab.

Important

The Pulse Installation Package status should be Complete.

- b. Click on the related icon and choose **Install** to open the IP Deployment Wizard.
- c. Fill required fields and finish the installation.

Important

- For IPCCommon, the InstallPath should be an empty folder for the Pulse installation (for example, C:\123).
- When installing Pulse on Linux, a second path leading to the GAX installation (the field is called GAX directory) must be specified in addition to InstallPath.

Tip

You can also install Pulse directly on the server by executing the Pulse installation procedure from the Pulse installation package.

If the installation procedure fails to find the GAX installation, you can manually copy the following files to enable Pulse in GAX: pulse.jar, pulse-proto.jar, and protobuf-java-2.5.0.jar from the Pulse installation: <GAX root>/webapp/WEB-INF/lib/ on Linux or <GAX root>\webapp\WEB-INF\lib on Windows.

3. Optional: Configure the [Pulse] options on **Application Options** tab for the GAX Application object:

Important

During startup, GAX looks for all options that are required for Pulse operation and adds them to the GAX Application object if they are not explicitly configured. If a required option is either not configured or specifies an invalid option value, GAX uses the option's default value.

4. Create a new Database Access Point, which is necessary for connectivity to the Pulse database:
 - a. On the **General** tab, set the **Connection Type** to **JDBC** and specify the following field values:
 - Role = Main
 - Debug = false
 - JDBC Query Timeout: 15
 - Case Conversion: any
 - b. On the **Ports** tab, change the value of the default port to the value of your RDBMS port.
 - c. On the **Application Options** tab, add the role configuration option with its value set to pulse in the

GAX section to identify this Database Access Point as the database schema created for Pulse.

- d. For a PostgreSQL database, add the `postgre_71_compatible` configuration option with its value set to `false` in the GAX section on the **Application Options** tab.

Refer to the [Framework 8.0 DB Server User's Guide](#) for additional information about configuring this application.

- Add the Database Access Point to the connections of your GAX Application object.
- Navigate to **Configuration > Environment > Application**, select the GAX Application, **Permissions** tab and configure the SYSTEM account to have Read, Update, and Execute permissions.
- For a High Availability (HA) deployment,
 - a. Complete Steps 2-6, for each GAX Application object to be used with the Pulse plug-in.
 - b. Each GAX application should have the other GAX application in its connections and there must be no relation between the GAX applications as Backup Servers.
 - c. Navigate to GAX application object properties and select Application options tab to create a new [pulse] section.
 - d. Set the `access_url` option in the [pulse] Section on the **Application Options** tab of the GAX Application object for each instance of GAX.

Important

Both Pulse instances must use the same database.

- From the user account created when you prepared the Pulse database, execute the SQL statements in the appropriate initialization script deployed during installation (scripts folder)—either:
 - `pulse_init_mssql.sql`
 - `pulse_init_oracle.sql`
 - `pulse_init_postgres.sql`
- Restart GAX. See the [GAX Deployment Guide](#) for information about how to start GAX.

5. Configure the Stat Server Application object.

Configuring the Stat Server **Application** object

Important

Stat Server requires Java Environment configuration for several

templates to function properly. See the [Stat Server Deployment Guide](#) for details. Without this additional configuration, statistics in some Queue templates (Email Queue Activity, eServices Queue KPIs, IWD Queue Activity) will not work.

1. Set the `accept-clients-in-backup-mode` option in the `[statsserver]` section on **Application Options** tab to `yes` for both the primary and backup Stat Server Application objects.

Important

This option is required even if there is no backup application specified for the Stat Server application.

2. Update `stattypes` specified in the `pulse_statistics.cfg` file within the `scripts` folder in Pulse installation to use the particular social media that is configured in your eServices solution (facebook is used in default file version). See [eServices documentation](#) for more details.
3. You must import `pulse_statistics.cfg` file to both the primary and backup Stat Server Application objects to create the `stattypes` that Pulse should monitor. To monitor the file:
 - a. Click **More** on the **Application Options** tab.
 - b. Select **Import**, uncheck **Override**, and browse the file.

Important

- To calculate the **% Ready Time** in the Queue KPIs template, set the `queue-use-pseudo-actions` option in the `[statsserver]` section of Stat Server Application object to `false`.
- Some Stat Server filters used in Pulse templates rely on certain user data or reasons attached to the call (for example, `VoiceCall_No_Wait`, `ReasonLunch`, and others that have `PairExists` in their definition).

You may need to adjust definitions of these filters to use `Attached Data` or `Reasons` according to your environment or adjust your routing strategies or desktop application to attach data used by those statistics. Otherwise, statistics that rely on these filters will show 0 (zero).

4. Restart both Stat Server applications.

6. Configure user access.

Configuring User Access

1. In GAX, navigate to **Configuration > Accounts > Roles** and create a new Role object to provide access to Pulse functionality.

Important

When creating a new Role, a dialog box with Role Template Selection appears. Do not select a template (leave the selection empty). Press **OK**.

- a. Define the privileges granted by the Role on the **Assigned Privileges** tab in the Pulse section.

[+] Privilege Details

Privileges manage the following item access:

- default dashboard
- templates
- widget definition, including objects, statistics, and refresh rate
- widget display options, including widget type, statistics to display, and alerts
- statistical data provided through the widget
- custom dashboard

Privileges Defined:

- **Pulse Read Layout**—See data provided by a widget. Configure the custom dashboard, including reset it to Default.
- **Pulse Update Layout**—Edit widget display options.
- **Pulse Write Layout**—Remove, create, clone, and edit widgets.
- **Pulse Write Template**—Remove, create, clone, and edit custom templates. Change the default dashboard.

Important

Users without permission to edit their own Person object cannot save their Custom dashboard configuration. Users without permission to edit both their own Person object and their Tenant object cannot save the Default dashboard configuration. For example, such a user can make changes, such as creating widgets, but cannot save the changes. The next time the page is loaded, the changes are lost.

Pulse privileges use GAX logic, so the high-level privileges do not include lower-level privileges. For example, to configure role with full control access, you have to assign all four privileges to it.

For role members to create Widgets, you must assign **Pulse Read Layout** and **Pulse Update Layout** in addition to **Pulse Write Layout**.

Important

You must assign at least the **Pulse Read Layout** privilege to each Role object.

- b. Assign the Role to Persons and Access Groups in the Role Members section as required.
2. Update the GAX User to have the following permissions:
 - Read and execute permissions on the client application (usually called default)
 - Read and execute permissions on Tenant
 - Read and update permission on their own Person object

Important

Users without permission to edit their own Person object cannot save their Custom dashboard configuration. Users without permission to edit both their own Person object and their Tenant object cannot save the Default dashboard configuration. For example, such a user can make changes, such as creating widgets, but cannot save the changes. The next time the page is loaded, the changes are lost.

- a. Provide the user permission to modify the tenant configuration object.
 - i. Select Configuration.
 - ii. From the Environment pane, choose Tenants.
 - iii. Click to open the required Tenant to view its properties.
 - iv. Select Permissions tab.
 - v. Add the Person or Access group containing this user.
 - vi. Add Update permission in addition to Read and Execute already required to access GAX.
- b. Provide the user permission to modify the user's own configuration object:
 - i. Select Configuration.
 - ii. From the Accounts pane, choose Persons.
 - iii. Click to open the required Person's properties.

- iv. Select Permissions tab.
- v. Add the Person or Access group containing this user.
- vi. Add set Update permission.

Pulse Configuration Options

The application templates for Pulse might contain other configuration options that are not described in this chapter. These options must remain set to the default values that are provided in the application templates. Changing these values might cause unexpected behavior.

You are not required to configure any options to start Pulse. Pulse supplies default values for all options that it requires to function.

GAX Application Object

[pulse] Section

access_url

Valid Values: `http://<gax_host>:<gax_port>`

where:

`gax_host`—The name or IP address of the GAX host computer

`gax_port`—The port of the GAX server

For example: `http://pulsedev01:8280/gax`

Default Value: `http://host:port`

Changes Take Effect: After restart

Specifies the URL of the Genesys Administrator Extension (GAX) in which Pulse has been configured. Configure this option only for High Availability (HA) configuration. You must configure this option for every GAX instance. For example, configure GAX1 host computer information for «`access_url`» GAX1 and GAX2 host computer information for «`access_url`» GAX2. If Pulse is behind a network load balancer, then both URLs should be empty.

Pulse shows the `Collector does not respond` error containing a link to the Pulse backup if available when the `access_url` option is configured and not empty.

Pulse shows the latest available data even if `Collector` is down, along with a `Collector does not respond` error when `access_url` option is empty.

Note: The URL must be accessible from the Pulse user network. If Pulse is behind a load balancer, then `access_url` should be empty. In scenarios with a load balancer, the health-check must be configured.

cache_expire_timeout

Valid Values: zero or any positive number

Default Value: 1200

Changes Take Effect: After restart

Specifies how long, in seconds, that Pulse stores the results of the object accessibility check in order to reduce the load on the Configuration server.

editable_templates

Valid Values: `true`,`false`

Default Value: false

Changes Take Effect: After restart

Enables users with appropriate permissions to edit Genesys-provided templates. If false, even and Administrator cannot edit the default templates. Use this option to remove obsolete or unused templates (for example, iWD or Email). Use in conjunction with the `install_templates` option.

health_expire_timeout

Valid Values: zero or any positive number

Default Value: 30

Changes Take Effect: After restart

Specifies how long, in seconds, Pulse stores result of previous health check, which includes the heartbeat, DB connection, and Configuration Server connection.

install_templates

Valid Values: true,false

Default Value: true

Changes Take Effect: After restart

Used in conjunction with the `editable_templates` option, specifies whether Pulse installs or updates the Genesys-provided templates for the current release when Pulse starts. In most cases, when `editable_templates` is true this option should be set to false.

For example, if you set `editable_templates` option to true, delete or edit some templates and the `install_templates` option is set to true, then Pulse restores all original Genesys-provided templates after restart for the current release. Pulse restores only templates from the current release, not earlier releases, which may be obsolete.

snapshot_expire_timeout

Valid Values: positive integer

Default Value: 24

Changes Take Effect: After restart

Specifies how long, in hours, that the snapshot file remains before Pulse automatically removes it.

This setting should be no more than 24 hours, unless you plan to provide enough disk space to store additional snapshots.

Pulse Collector Application Object

[collector] Section

hostname

Valid Values: Valid host name

Default Value: Empty value

Changes Take Effect: After restart

Specifies the Simple Network Management Protocol (SNMP) host name.

management-port

Valid Values: Positive integers

Default Value: No default value

Warning! No other application should use this port.

Changes Take Effect: After restart

Specifies the TCP/IP port that Pulse Collector reserves for SNMP Option Management Client connections. If this option is absent or null, a server for Management Client is not created.

Warning! You must specify a value for this option if you are using an SNMP connection. Do not change the value for this option while Pulse Collector is running.

output-transport

Default Value: No default value (but the application template supplies the preconfigured transport name of gpb-out)

Valid Values: the names of all transport protocols that you have defined in the [transport-gpb-out] section.

Changes Take Effect: After restart

Specifies the output transport to be used to produce outputs.

[configuration-monitoring] Section

check-layout-presence-timeout

Valid Values: 0-3600

Default Value: 900

Changes Take Effect: After restart

Specifies how often, in seconds, Pulse Collector checks for the deleted layouts. A zero (0) value completely disables the check.

Note: This defines the minimum timeout between two checks. The actual timeout depends on the database polling cycle, because the check is conducted after finishing subsequent database polling cycle.

db-poll-period

Valid Values: 3-3600

Default Value: 30

Changes Take Effect: After restart

Specifies how often, in seconds, Pulse Collector obtains updates from the Pulse database.

Note: Genesys recommends that you set this option to no less than 15 seconds.

excluded-objects-propagation-delay

Valid Values: 0...3600

Default value: 60

Changes Take Effect: Immediately

Specifies the delay in seconds before Pulse Collector attempts to propagate excluded objects in the affected layouts after an object is deleted. A zero value eliminates the timeout and Pulse Collector attempts to propagate excluded objects immediately after an object is deleted.

metagroup-contents-recheck-delay

Valid Values: 0...3600

Default Value: 60

Changes Take Effect: Immediately

Specifies the delay in seconds between when Pulse Collector verifies metagroup contents (such as Agent Group, Place Group, and DN Group) after notification from Configuration Server notifies Pulse Collector about changes in the contents of the metagroup object. Zero value of this option eliminates

timeout and metagroup change is processed immediately.

Note: This configuration option impacts ANY changes in the metagroup (for example, both adding and deleting objects), so new objects added to the metagroup appear in the layout after the specified delay.

new-object-delay

Valid Values: 0-86400

Default Value: 0

Changes Take Effect: Immediately

Specifies the delay, in seconds, between when Pulse Collector receives notification of a new object in Configuration Server, and when it starts to process this notification. Setting this option to 0 enables Pulse Collector to process new objects without delays.

ods-wait-timeout

Valid Values: 10-3600

Default Value: 300

Changes Take Effect: After restart

Specifies the time, in seconds, that Pulse Collector waits before re-checking the Pulse database for proper initialization.

remove-dynamic-object-delay

Valid Values: 0-600

Default Value: 60

Changes Take Effect: After restart

Specifies the time, in seconds, that Pulse Collector waits before excluding and closing statistics for the Agent from affected layout that was excluded from the StatServer-based VAG. A zero value turns off the delay and Pulse Collector processes changes immediately.

[heartbeat] Section

heartbeat-folder

Valid Values: Valid folder path

Default Value: ./output/heartbeat (as provided by template file)

Changes Take Effect: After restart

Specifies the path in which Pulse Collector writes the heartbeat file.

Note: Relative file paths must begin with ./

heartbeat-period

Valid Values: 3-3600

Default Value: 30

Changes Take Effect: After restart

Specifies the period of a heartbeat update, in seconds.

heartbeat-success-condition

Valid Values:

One or any combination of the following conditions:

- statsserver—Stat Server connection should be available.

- snapshot-writer—The snapshot writer should be producing outputs without error.
- collector-db—The main DB connection should be available.

Default Value: statsserver, snapshot-writer

Changes Take Effect: After restart

Specifies a comma-separated list of conditions to be checked for criteria of heartbeat success, which means the heartbeat is updated only if this criteria is met.

[layout-validation] Section

enable-layout-validation

Valid Values: yes,no

Default Value: yes

Changes Take Effect: After restart

Enables or disables layout validation in Pulse Collector.

Note: Pulse Collector always checks for consistency of LayoutID and TenantID. These validations apply even if options are set to a value no.

validate-strict-tenant-security

Valid Values: yes,no

Default Value: yes

Changes Take Effect: After restart

Enables Pulse Collector to fail the layout validation when the option strict-tenant-security in the configuration-monitoring section is set to yes and Pulse encounters an individual object that belongs to a tenant that is different than layout's tenant.

[limits] Section

max-formulas-per-layout

Valid Values: 1-100000

Default Value: 50

Changes Take Effect: After restart

Specifies the maximum number of formula-based statistics for each layout.

max-metagroups-per-layout

Valid Values: 1-100000

Default Value: 50

Changes Take Effect: After restart

Specifies the maximum number of metagroups for each layout.

max-objects-per-layout

Valid Values: 1-100000

Default Value: 400

Changes Take Effect: After restart

Specifies the maximum number of objects for each layout.

max-statistics-per-layout

Valid Values: 1-100000

Default Value: 100

Changes Take Effect: After restart

Specifies the maximum number of statistics for each layout.

[localization] Section

default-snapshot-message-language-code

Valid Values: Language code (non-empty string, typically 2 letters)

Default Value: en

Changes Take Effect: After restart

Specifies the default language code to use for layout snapshot messages, if the layout snapshot does not override this value.

language-pack-folder

Valid Values: Folder path

Default Value: ./messages

Changes Take Effect: After restart

Specifies the folder from which Pulse Collector reads localized message files to show layout errors in the localized form.

Note: Relative file paths must begin with ./

[Log] Section

all

Valid Values:

- **stdout**—Log events are sent to the Standard output (stdout).
- **stderr**—Log events are sent to the Standard error output (stderr).
- **network**—Log events are sent to Message Server, which can reside anywhere on the network. Message Server stores log events in the Log Database.

Setting the all log-level option to network enables Data Sourcer to send log events of Standard, Interaction, and Trace levels to Message Server. Log events of Debug level are neither sent to Message Server nor stored in the Log Database.

- **memory**—Log events are sent to the memory output on the local disk. This output is the safest in terms of the application performance.
- **[filename]**—Log events are stored in a file with the specified name. If you do not specify a path, the file is created in the application's working directory.

Default Value: stdout

Changes Take Effect: Immediately

Specifies the outputs to which Data Sourcer sends all log events. You must separate log-output types with commas when you configure more than one output type.

For example, all = stdout, logfile

Note: To ease the troubleshooting process, consider using unique names for log files that different applications generate.

buffering

Default Value: false

Valid Values: true,false

Changes Take Effect: Immediately

Specifies whether the operating system file buffering is on or off. This option applies only to stderr and stdout output. Setting this option to true increases output performance.

Note: When you enable buffering, log messages might appear in the log after a delay.

segment

Valid Values:

- false—No segmentation allowed.
- <number> KB or <number>—Sets the maximum segment size in kilobytes. The minimum segment size is 100 KB.
- <number> MB—Sets the maximum segment size, in megabytes.
- <number> hr—Sets the number of hours for which the segment stays open. The minimum number is 1 hour.

Default Value: 10 MB

Changes Take Effect: Immediately

Specifies if there is a segmentation limit for a log file. If there is, this option sets the unit of measurement along with the maximum size. If the current log segment exceeds the size set by this option, the current file is closed and a new file is created.

verbose

Valid Values:

- all—All log events (that is, log events of Standard, Trace, Interaction, and Debug levels) are generated if you set the debug-level option in the statsserver section to all.
- debug—The same as all.
- trace—Log events of the Trace and higher levels (that is, log events of Standard, Interaction, and Trace levels) are generated, while log events of the Debug level are not generated.
- interaction—Log events of the Interaction and higher levels (that is, log events of Standard and Interaction levels) are generated, while log events of the Trace and Debug levels are not generated.
- standard—Log events of the Standard level are generated, while log events of the Interaction, Trace, and Debug levels are not generated.
- none—Produces no output.

Default Value: all

Changes Take Effect: Immediately Determines whether a log output is created. If it is, this option specifies the minimum level of log events that are generated. The log-event levels, starting with the highest-priority level, are Standard, Interaction, Trace, and Debug.

Refer to the Framework Deployment Guide or Framework Solution Control Interface Help for more information on the Standard, Trace, Interaction, and Debug log levels.

[object-name-format] Section

You can use a custom format for an object name, which can include a mix of predefined text and additions to the object properties within their actual values with optional width and trimming rules. For details, see “Valid object name format string” and “Object Information”.

AccessResource

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type DN with subtype Access Resource. For details, see “Object Properties” at the bottom of this section.

ACDPosition

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type DN with subtype ACD Position. For details, see “Object Properties” at the bottom of this section.

ACDQueue

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for the object of the of type DN with subtype ACD Queue. For details, see “Object Properties” at the bottom of this section.

Agent

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for the object of the of type Agent. For details, see “Object Properties” at the bottom of this section.

AgentGroup

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for the object of the of type Agent Group. For details, see “Object Properties” at the bottom of this section.

CallingList

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type Calling List. For details, see “Object Properties” at the bottom of this section.

Campaign

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type Campaign. For details, see “Object Properties” at the bottom of this section.

CampaignCallingList

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type Campaign Calling List. For details, see “Object Properties” at the bottom of this section.

CampaignGroup

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type Campaign Group. For details, see “Object Properties” at the bottom of this section.

Cellular

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type DN with subtype Cellular. For details, see “Object Properties” at the bottom of this section.

Chat

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type DN with subtype Chat. For details, see “Object Properties” at the bottom of this section.

CoBrowse

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type DN with subtype CoBrowse. For details, see “Object Properties” at the bottom of this section.

CP

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type DN with subtype CP. For details, see “Object Properties” at the bottom of this section.

Data

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type DN with subtype Data. For details, see “Object Properties” at the bottom of this section.

DN

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type DN. For details, see “Object Properties” at the bottom of this section.

DNGroup

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type DN Group. For details, see “Object Properties” at the bottom of this section.

EAPort

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type DN with subtype EA Port. For details, see “Object Properties” at the bottom of this section.

Email

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type DN with subtype Email. For details, see “Object Properties” at the bottom of this section.

Extension

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type DN with subtype Extension. For details, see “Object Properties” at the bottom of this section.

ExtRoutingPoint

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type DN with subtype Ext Routing Point. For

details, see “Object Properties” at the bottom of this section.

FAX

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type DN with subtype Fax. For details, see “Object Properties” at the bottom of this section.

Mixed

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type DN with subtype Mixed. For details, see “Object Properties” at the bottom of this section.

Music

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type DN with subtype Music. For details, see “Object Properties” at the bottom of this section.

Place

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type Place. For details, see “Object Properties” at the bottom of this section.

PlaceGroup

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type Place Group. For details, see “Object Properties” at the bottom of this section.

RoutingPoint

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type DN with subtype Routing Point. For details, see “Object Properties” at the bottom of this section.

RoutingQueue

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type DN with subtype Routing Queue. For details, see “Object Properties” at the bottom of this section.

RoutingStrategy

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type DN with subtype Routing Strategy. For details, see “Object Properties” at the bottom of this section.

Script

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type Script. For details, see “Object Properties” at the bottom of this section.

ServiceNumber

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type DN with subtype Service Number. For details, see “Object Properties” at the bottom of this section.

StagingArea

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type Script with subtype Staging Area. For details, see “Object Properties” at the bottom of this section.

Switch

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type Switch. For details, see “Object Properties” at the bottom of this section.

Tenant

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type Tenant. For details, see “Object Properties” at the bottom of this section.

Video

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type DN with subtype Video. For details, see “Object Properties” at the bottom of this section.

VirtACDQueue

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type DN with subtype Virt ACD Queue. For details, see “Object Properties” at the bottom of this section.

VirtRoutingPoint

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type DN with subtype Virt Routing Point. For details, see “Object Properties” at the bottom of this section.

VoiceMail

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type DN with subtype Voicemail. For details, see “Object Properties” at the bottom of this section.

VoIP

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type DN with subtype VoIP.

Workbin

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type Script with subtype Workbin. For details, see “Object Properties” at the bottom of this section.

Workflow

Valid Values: Valid object name format string. For details, see the table at the bottom of this section.

Default Value: %ObjectName%

Changes Take Effect: After restart

Specifies the object name formatting rule for an object of type DN with subtype Workflow For details, see “Object Properties” at the bottom of this section.

Valid object name format string

The valid object name format string is free text string, which allows values of object properties: %<PropertyName>:<side><padding><length>%

- **PropertyName**—Specifies the property name.
Note:Property names are case sensitive.
- **side**—Specifies the side, L (left) or R (right) , from where the length must be counted. If you do not specify a side, Pulse uses L by default.
L is commonly used for string or text properties.
R is commonly used for numbers.
- **padding**—Specifies the padding when the property value length is less than the specified custom length
. (dot) to pad with space characters
0 (zero) to pad with zero characters.
- **length**—Specifies the maximum number of characters for the property name.

Valid Object Name Format String	Description
<ul style="list-style-type: none"> • %EmployeeID:10% • %EmployeeID:L10% 	Both specify 10 characters of property EmployeeID from the left side.
<ul style="list-style-type: none"> • %EmployeeID:.10% • %EmployeeID:L.10% 	Specifies 10 characters of property EmployeeID from left, but if length was less than 4 symbols, pad it with spaces.
<ul style="list-style-type: none"> • %DBID:R4% 	Specifies 4 characters of property DBID from the right side.
<ul style="list-style-type: none"> • %DBID:R04% 	Specifies 4 characters of property DBID from the right side, but if the length is less than 4 characters, pads it with zeros.

Object Properties

The table below lists the object properties available for use in the format strings.

Object Type	Property	Description
All Object Types	DBID	Specifies the ID of the object. For example, Campaign Group is in group DBID, Campaign Calling List is in CallingList ID.
All Object Types	ObjectID	Specifies the ID number of the object in Pulse Collector. Notes: <ul style="list-style-type: none"> • This is the typically the configuration layer DBID, but

Object Type	Property	Description
		<p>for some types of objects (for example, Campaign Group, Campaign Calling List) this is a composite 64-bit ID.</p> <ul style="list-style-type: none"> The composite 64-bit ID is an unsigned 64-bit number with the following composition: <ul style="list-style-type: none"> higher 32 bits: DBID of Campaign lower 32 bits: DBID of Calling List or Agent/Place group
All Object Types	ObjectName	Specifies the name of the object, which is written to the snapshot file.
All Object Types	ObjectType	Specifies the type of the object.
All Object Types	TenantID	Specifies the Tenant ID of the object.
All Object Types	type	Specifies the type of the object.
Agent	EmailAddress	Specifies the email address of the agent (person).
Agent	EmployeeID	Specifies the employee ID of the agent (person).
Agent	ExternalID	Specifies the external ID of the agent (person).
Agent	FirstName	Specifies the first name of the agent (person).
Agent	LastName	Specifies the last name of the agent (person).
Agent	UserName	Specifies the user name of the agent (person).
Calling List	Description	Describes the calling list.
Campaign	Description	Describes the campaign.
Campaign Calling List	CallingListDescription	Describes the underlying Calling List object.
Campaign Calling List	CallingListName	Specifies the DBID of the Calling List object.
Campaign Calling List	CampaignDBID	Specifies the DBID of the Campaign object.
Campaign Group	CampaignDBID	Specifies the DBID of the Campaign object.
Campaign Group	GroupDBID	Specifies the DBID of the group object.

Object Type	Property	Description
Campaign Group	GroupType	Specifies the numeric Type of the group object (CFGAgentGroup or CFGPlaceGroup).
DN, Routing Queue, Routing Point	Alias	Specifies the DN Alias.
DN, Routing Queue, Routing Point	AliasOrNumber	Populated with the DN Alias if available, otherwise populated with the DN number.
DN, Routing Queue, Routing Point	Number	Specifies the DN number.
DN, Routing Queue, Routing Point	SwitchDBID	Specifies the switch DBID.
DN, Routing Queue, Routing Point	SwitchID	Specifies the switch name.
Routing Strategy, Staging Area, Workbin	ScriptType	Specifies the script type ID.
Switch	DNRange	Specifies the switch DN Range.
Switch	SwitchType	Specifies the switch type.

[output] Section

collector-snapshot-log-level

Valid Values: Debug, Info, Warning, Error, Fatal, Unknown, None (case-insensitive)

Default Value: Warning

Changes Take Effect: After restart

Determines minimum log level for snapshot message that is written to Pulse Collector log.

max-output-interval

Default Value: 3600

Valid Values: 3-3600

Changes Take Effect: After restart

Specifies the maximum allowed output interval for all report layouts. Users can independently set output frequencies by layout within the Pulse user interface. If the set frequency, however, is greater than the value of this option, Pulse uses the value of this option instead.

Note: The value of this option must be greater than the value of the min-output-interval option or Pulse Collector logs an appropriate error.

min-output-interval

Default Value: 3

Valid Values: 3-3600

Changes Take Effect: After restart

Specifies the minimum allowed output interval for all report layouts. Users can independently set output frequencies by layout within the Pulse user interface. If the set frequency, however, is less than the value of this option, Pulse uses the value of this option instead.

snapshot-log-level

Valid Values: Debug, Info, Warning, Error, Fatal, Unknown, None (case-insensitive)

Default Value: Info

Changes Take Effect: After restart

Specifies the minimum log level for a snapshot message that is put to a layout snapshot.

[parallel-processing] Section

snapshot-builder-worker-thread-count

Valid Values: 1-128

Default Value: 1

Changes Take Effect: After restart

Defines the number of concurrent threads used to build snapshots.

[scripting] Section

definition-script-execution-timeout

Valid Values: 1-900

Default Value: 45

Changes Take Effect: After restart

Time in seconds allowed for definition script execution.

formula-script-execution-timeout

Valid Values: 1-900

Default Value: 5

Changes Take Effect: After restart

Time in seconds allowed for single formula evaluation script execution.

init-script-execution-timeout

Valid Values: 1-900

Default Value: 60

Changes Take Effect: After restart

Time in seconds allowed for initialization script execution.

js-lib-path

Valid Values: Valid folder paths

Default Value: ./jslib/standard

Changes Take Effect: After restart

Comma-separated list of locations of the directories that contain additional JavaScript libraries to be used within the formula scripting engine.

Note: Relative file paths must begin with ./

js-modules

Valid Values: Comma-separated list of JavaScript files

Default Value: collector.js,cfllib.js,statlib.js,gts.js

Changes Take Effect: After restart

Comma-separated list of modules to preload into the scripting engine.

stop-compute-formula-threshold-for-snapshot

Valid Values: 0-100

Default Value: 3

Change Take Effect: After restart

Specifies the maximum allowed number of `timeout_expired` errors during formula computation, after which, Pulse Collector assigns the particular formula-based statistic the `ERROR` value for the current snapshot. A zero value of this option suppresses the limit of the `timeout_expired` failures.

[`statistic-request-handling`] Section

always-use-statserver-newapi

Valid Values: yes, no

Default Value: no

Changes Take Effect: After restart

Determines whether to force Pulse Collector to request all statistics through the StatServer New API that uses the proper parameter set.

data-flow-check-interval

Default Value: 360

Valid Values: 5–3600

Changes Take Effect: After restart

Recommended Values: Positive integers that are less than the maximum notification interval value, either with reset-based notification using the time profile or time-based notification using the notification interval parameter.

Note: Standard Pulse layouts use a 60 second notification interval.

Changes Take Effect: Immediately

How often, in seconds, Pulse Collector verifies that there is data flow from Stat Server (primary and backup), provided that Pulse Collector contains active report layouts and has a live connection to Stat Server.

data-flow-timeout

Default Value: 120

Valid Values: 5–86400

Changes Take Effect: After restart

Recommended Values: Positive integers that are greater than the value that you specify for `data-flow-check-interval` and less than two times of the maximum notification interval value, either with reset-based notification using time profile or time-based notification using notification interval parameter.

Note: Standard Pulse layouts use a 60 second notification interval.

Changes Take Effect: Immediately

Time, in seconds, that is acceptable to suspend the transfer of data from Stat Server (primary or backup), provided that Pulse Collector contains active report layouts and has a live connection to Stat Server. The timer starts upon the last successful data transfer.

data-source-choice-strategy

Valid Values: `PrimaryRunMode`, `LastGood`, `FirstAvailable`, `MostUpToDate`, `PrimaryInCME`

Note: All values are case-insensitive.

Default Value: `PrimaryRunMode`

Changes Take Effect: After restart

Specifies which StatServer configured in the configuration layer that Pulse Collector uses as a data source for a snapshot:

- `PrimaryRunMode`—Pulse Collector uses the StatServer running in the primary mode. If both Stat Servers appear to be backup, Pulse Collector attempts the next strategy.

- **LastGood**—Pulse Collector uses the last good StatServer if available. Otherwise, Pulse Collector attempts the next strategy.
- **FirstAvailable**—Pulse Collector uses the Primary StatServer if available. If uses the Primary StatServer is unavailable, Pulse Collector uses the Backup StatServer. Otherwise, Pulse Collector attempts the next strategy.
- **MostUpToDate**—Pulse Collector uses StatServer that sent statistic data with most recent Server Time. Otherwise, Pulse Collector attempts the next strategy.
- **PrimaryInCME**—Pulse Collector always uses the Primary StatServer.

statserver-batch-size

Valid Values: 1-10000

Default Value: 500

Changes Take Effect: Immediately

Specifies the number of statistic requests sent to Stat Server in a single packet. The recommended value depends on the number of statistic requests you plan to run, network bandwidth, and processing capabilities of the Stat Server and Pulse Collector servers. If Stat Server disconnects Pulse Collector when it is opening statistics with error message Client too slow, decrease value of this option.

statserver-profiles-timeout

Valid Values: 1-86400

Default Value: 600

Changes Take Effect: Immediately

Specifies the timeout, in seconds, to receive and process server profiles from Stat Server. If profiles are not received and processed within the given timeout, Pulse Collector closes the current connection to StatServer and attempts to reconnect.

suspend-statistic-notifications-for-paused-layouts

Valid Values: yes, no

Default Value: no

Changes Take Effect: After restart

Determines whether to suspend the statistic notifications for paused layouts.

Note: You must have Stat Server version 8.1.200.17 or higher for this functionality to work correctly, if you set the value of suspend-statistic-notifications-for-paused-layouts to yes.

verbose-request-statistics

Valid Values: true, false

Default Value: false

Changes Take Effect: Immediately

Determines whether to enable Pulse Collector to log verbose messages about the objects for which it requests statistics.

[transport-gpb-out] Section

output-file-ext

Valid Values: Valid file extensions for your operating system

Default Value: gpb

Changes Take Effect: After restart
Specifies the file extension for the full output file format.

output-file-mode

Valid Values: 0-0777

Default Value: 0664

Changes Take Effect: After restart

On Linux, specifies the UNIX mode for each output file created by this transport.

Important! This option respects umask set at OS level.

output-folder

Valid Values: Valid folder paths

Default Value: No default (the collector.apd file supplies the value of a sample output directory)

Changes Take Effect: After restart

Specifies the path in which Pulse Collector writes output files. If you specify a folder that does not exist, Pulse Collector creates it for you.

Note: Relative file paths must begin with ./

transport-type

Default Value: file

Valid Values: file

Changes Take Effect: After restart

Specifies the transport output type.

Starting and Stopping Pulse

Pulse starts and stops automatically when Genesys Administrator Extension (GAX) starts and stops.

Prerequisites

Confirm the following requirements before starting Pulse:

- a. See [Browser Support for Pulse](#) in the *Genesys Supported Operating Environment Reference Guide*.
- b. Your monitor must be set to a resolution of no less than 1024x768.
- c. The DB Server for Pulse Collector must be running.
- d. The RDBMS for the Pulse database must be running.
- e. Configuration Server and the DB Server for Configuration Server must be running.

Important

Users without permission to edit their own Person object cannot save their Custom dashboard configuration. Users without permission to edit both their own Person object and their Tenant object cannot save the Default dashboard configuration.

For example, such a user can make changes, such as creating widgets, but cannot save the changes. The next time the page is loaded, the changes are lost.

See the steps to [configure user access](#) for details.

Starting and Stopping Pulse Collector

You can start Pulse Collector on a Windows or UNIX platform. Invoking Pulse Collector starts a series of internal checks for proper configuration. The value of the `max-output-interval` option, for example must be greater than the value of the `min-output-interval` option or Pulse Collector exits. Verify your Collector Application object for proper configuration before starting Pulse Collector.

Prerequisites

The following must be running prior to starting Pulse Collector:

- **Backup Configuration Server**

To restart the Pulse Collector application when the backup Configuration Server switches to the primary mode, you must specify the backup Configuration Server parameters when starting Pulse Collector.

On the command line, specify these parameters using the following two arguments:

- `-backup_host hostname`
- `-backup_port port-number`

- **National Characters**

To use national characters in the string properties correctly, Pulse Collector determines which multibyte encoding is used by Configuration Server. You can allow Pulse Collector to use the default setting or specify the characters by editing the following configuration options:

- **Windows**

You can specify Configuration Server multibyte encoding through the command-line parameters:

- `-cs_codepage` following the Windows code page number (for example, 1251). For more information about Windows code pages and their numbers, see [http://msdn.microsoft.com/en-us/library/windows/desktop/dd317756\(v=vs.85\).aspx](http://msdn.microsoft.com/en-us/library/windows/desktop/dd317756(v=vs.85).aspx). If the parameter is not specified, Pulse Collector assumes Configuration Server uses the code page that corresponds to the locale of the Windows operating system where Pulse Collector is running.
- `-cs_encoding`. It accepts Microsoft-compatible symbolic name of locale and results choice of default code page for that locale. For more information about Microsoft-compatible locale names, see <http://msdn.microsoft.com/en-us/library/dd373814.aspx>

Important

{{{1}}}

- **Linux**

You can specify Configuration Server multibyte encoding through the command-line parameter `-cs_encoding` following the iconv-compatible symbolic name of encoding (for example, UTF-8).

To display the list of encodings supported on the your system, enter the following command in the Linux console:

```
iconv --list
```

Start Pulse Collector

Starting Pulse Collector

You can start Pulse Collector on any of the supported platforms.

Solution Control Interface (SCI)

You can start Pulse Collector:

[+] From SCI.

To start Pulse Collector from the Solution Control Interface (SCI):

1. From the Applications view, select your Pulse Collector Application object in the list pane.
2. Click the Start button on the toolbar, or select Start either from the Action menu or the context menu. (Right-clicking your Application object displays the context menu.)
3. Click Yes in the confirmation box that appears. Your Pulse Collector application starts.

For information about how to use SCI, refer to *Framework 8.0 Solution Control Interface Help*.

Windows

On a Windows platform, you can start Pulse Collector:

[+] Manually from the Programs menu as an application.

To start Pulse Collector from the Programs menu as an application, select Start Pulse Collector from the program group created during installation. The application opens a console window and automatically issues the parameters specified during configuration to start Pulse Collector. The Pulse Collector application name, version, and connectivity parameters appear in the title bar.

[+] Manually from a console window as an application.

1. To start Pulse Collector as an application from a console window: At the command-line prompt, go to the directory where Pulse Collector has been installed. Type the name of the Pulse Collector executable followed by the appropriate command-line parameters using the following syntax:

```
pulse_collector.exe -host hostname -port portno -app application
```

where:

- hostname refers to the name of the computer on which Configuration Server is running.
- portno refers to the communication port on which Configuration Server is running.

- application refers to the name of the Pulse Collector Application object as defined in Genesys Administrator.

Important

If the host or application name contains spaces or hyphens (-), enclose it in double quotation marks.

For example, to start Pulse Collector with parameters specifying the host as cs-host, port as 2020, and name as Pulse Coll, type:

```
pulse_collector.exe -host "cs-host" -port 2020 -app "Pulse Coll"
```

Important

If needed, specify the optional parameters -backup_host, -backup_port, -cs_codepage, and -cs_encoding.

[+] As a Windows service.

1. From the task bar, choose Start - Administrative Tools > Computer Management.
2. Open Services and Applications > Services.
3. Right-click your Pulse Collector service from the list and select Start.

Important

Since the Local Control Agent (LCA) can be installed as a Windows service with the user interface disabled, all servers started through SCI, in this case, are started without a console unless you specifically select the Allow Service to Interact with Desktop check box for both LCA and Pulse Collector.

UNIX Platforms

You can start Pulse Collector:

[+] Manually from UNIX Platforms.

1. Go to the directory where Pulse Collector has been installed.

Important

You can invoke Pulse Collector only from the directory in which it was installed.

2. Type the name of the Pulse Collector executable followed by the appropriate command-line parameters using the following syntax:

```
./pulse_collector -host hostname -port portno -app application
```

where:

- hostname refers to the name of the computer on which Configuration Server is running.
- portno refers to the communication port on which Configuration Server is running.
- application refers to the name of the Pulse Collector Application object as defined within Genesys Administrator.

Important

If the host or application name contains spaces or hyphens (-), enclose it in double quotation marks.

For example, to start Pulse Collector with parameters specifying the host as cs-host, port as 2020, and name as Pulse Coll, type:

```
./pulse_collector -host "cs-host" -port 2020 -app "Pulse Coll"
```

Important

If needed, specify the optional parameters -backup_host, -backup_port, and -cs_encoding.

Configure the stdout option in the log section of collector options to write to a log file, so that you can check for errors in its configuration if Pulse Collector fails to start. If you cannot resolve a problem, contact Genesys Customer Care and provide the entire content of the log.

You can also type the name of the Pulse Collector executable and its command-line parameters into a shell script and execute the script using the following command:

```
./run.sh [Name of script]
```

To redirect Pulse Collector output (on most UNIX shells), use the following syntax:

```
./pulse_collector -host hostname -port portno -app appl > log_file.log
```

To have both log file and console, within Genesys Administrator add the following to Pulse Collector's application properties:

- Section: Log
- Option: all with the following value:
stdout,<log_file_name.log>,network
Separate values with commas. Instead of stdout, you can also specify stderr.

Pulse Collector writes messages to <log_file_name.log> in the same directory where Pulse Collector is installed. To have Pulse Collector write to a different location, specify the full path for this parameter.

End of procedure

Stop Pulse Collector

Stopping Pulse Collector

You can stop Pulse Collector on any of the supported platforms.

Important

Be sure that the autorestart property is cleared for the Pulse Collector Application object in Genesys Administrator.

Solution Control Interface (SCI)

You can stop Pulse Collector:

[+] From SCI.

If you use LCA and Solution Control Server (SCS), you can stop Pulse Collector from SCI. To do so:

1. From the Applications view, select your Pulse Collector Application object in the list pane.
2. Click Stop on the toolbar, or select Stop either from the Action menu or the context menu.
3. Click Yes in the confirmation box that appears.

On a Windows platform

On a Windows platform, you can stop Pulse Collector:

- **[+] Manually from its console window as an application.**
If Pulse Collector is running as an application, switch to its console window and press `Control-C` to stop it.
- **[+] As a Windows service.**

Starting and Stopping Pulse Collector

If you are running Pulse Collector as a Windows service, you should stop it only from the Microsoft Management Console.

To stop Pulse Collector running as a Windows service:

1. From the task bar, choose Start - Administrative Tools > Computer Management.
 2. Open Services and Applications > Services.
 3. Right-click your Pulse Collector service from the list and select Stop.
- If LCA and SCS are used, you can stop Pulse Collector from SCI.

On a Unix platform

Stop Pulse Collector on UNIX using either of the following methods:

- On the command line, type `kill -9 processid`, where `processid` is Pulse Collector's UNIX process ID.
- Press `^C` from the active Pulse Collector console.
- If LCA and SCS are used, you can stop Pulse Collector from SCI.

Application Files

The Pulse installation routine creates a root application folder with a scripts subfolders.

Pulse

The following files are found in the Pulse root folder and the scripts subfolder.

[+] Contents of the Pulse Root Folder

- ip_description.xml—File that stores the installation package content.
- protobuf-java-2.5.0.jar—Jar file that contains the Google Protocol Buffers library.
- pulse.jar—Executable Jar file.
- pulse-proto—Executable Jar file.
- read_me.html file—File that contains general information about this product release.
- templates.xls—File that contains template descriptions.
- dbtool—Folder that contains dbtool files.
- scripts subfolder—Subfolder containing:
 - Subfolders that hold the database initialization SQL scripts for each of the following RDBMS types:
 - Microsoft SQL
 - Oracle
 - PostgreSQL
 - pulse_statistics.cfg file—File that specifies the options needed for Stat Server to process Pulse preconfigured templates.
- thirdparty—Folder that contains third-party licenses and additional files as required.

[+] Contents of the scripts\[dbtype] Subfolder

- mssql\pulse_init_mssql.sql—Database initialization script for a Microsoft SQL RDBMS.
- oracle\pulse_init_oracle.sql—Database initialization script for an Oracle RDBMS.
- postgres\pulse_init_postgres.sql—Database initialization script for a PostgreSQL RDBMS.

Pulse Collector

Pulse Collector installation routine deploys the following files to the Collector root folder and its subfolders.

[+] Contents of the Pulse Collector Root Folder

- common.lms—File that stores common log messages.
- collector and collector.exe—Application executables for Unix and Microsoft Windows platforms.
- collector.lms—File that stores Pulse Collector-specific log messages.
- extras—Folder that stores file extra configuration options.
- ip_description.xml—File that stores installation package content.
- messages—Folder that stores localized error messages.
- pthreadVC2.dll—The pthreads-win32 library file.
- pthreadVC2.pdb—File that provides pthreads-win32 debugging information.
- run.sh—On UNIX platforms, shell script that launches Pulse Collector.
- startServer.bat—On Windows platforms, the batch file that starts Pulse Collector as a regular application, not as a Windows Service.
- thirdparty—Folder that contains third party licenses and additional files as required.
- jslib—Folder that contains two subfolders, extras and standard, which contain the JavaScript library files to be used by Pulse Collector.

[+] Contents of the Pulse Collector extras Folder

- finetuning.cfg—File that provides fine tuning configuration options.

[+] Contents of the Pulse Collector jslib/standard Folder

- cfglib.js—File that provides JavaScript definitions related to Configuration Server
- collector.js—File that provides JavaScript definitions for Pulse Collector.
- gts.js—File that provides set of additional JavaScript functions used in the standard Pulse layout templates
- statlib.js—File that provides JavaScript definitions for various constants on which Stat Server relies.

[+] Contents of the Pulse Collector messages Folder

- layout-en.msg—Localized message file.
- layout-ru.msg—Localized message file.
- layout-uk.msg—Localized message file.

Change History

This section lists content that is new or that has changed significantly since the first release of this content. The most recent changes appear first.

For *New in This Release* content, see the [Pulse landing page](#) for this release.

New in Document Version 8.5.0

The following topics have been added or changed since the previous release:

- The [Architecture diagram](#) was updated.
- Software requirements and deployments were updated in [Deploying Pulse Collector and Pulse](#).
- The step to execute `ALTER DATABASE <Pulse DB> SET READ_COMMITTED_SNAPSHOT ON;` was added to [Deploying the Pulse database](#) for the Microsoft SQL Server.
- [Starting Pulse](#) was updated.
- [Prerequisites and Starting Pulse](#) were updated.
- The following [Configuration Options](#) were changed:
 - Removed the [layout-history], [parallel-processing], [thresholds], and [transport-gpb-history] sections.
 - In the [collector] section:
 - Removed the history-transport option.
 - In the [configuration-monitoring] section:
 - Added the excluded-objects-propagation-delay and remove-dynamic-object-delay options.
 - Removed the auto-detect-dynamic-metagroups, enable-differential-layout-recheck, recheck-active-layout-definition, and strict-tenant-security options.
 - In the [layout-validation] section:
 - Renamed the enable-strict-tenant-security-validation-rule option to validate-strict-tenant-security.
 - In the [limits] section:
 - Removed the max-custom-actions-per-layout, max-custom-thresholds-per-layout, max-threshold-associations-per-layout options.
 - In the [output] section:
 - Added the collector-snapshot-log-level and snapshot-log-level option.
 - Removed the cleanup-output option.
 - In the [pulse] section:

- Added the `editable_templates`, `install_templates`, and `snapshot_expire_timeout` options.
- Removed the `pause_timeout` option.
- In the `[scripting]` section:
 - Added the `stop-compute-formula-threshold-for-snapshot` option.
 - Removed the `cumulative-formula-script-execution-timeout`, `cumulative-threshold-script-execution-timeout`, `enable-extended-statistic-value`, `post-processing-script-execution-timeout`, and `threshold-script-execution-timeout` options.
- In the `[statistics-request-handling]` section:
 - Removed the `optimize-statistic-requests` options.
- In the `[transport-gpb-out]` section:
 - Added the `output-file-mode` option.
 - Removed the `backend-file-ext`, `cleanup-file-modification-age-threshold`, `generate-layout-info-file`, and `output-format` options.