



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Configurations Options Reference Manual

[log] Section

12/18/2025

[log] Section

This section controls SCS logging.

This section must be called **log**.

Solution Control Server supports the log options described in this section in addition to those described in the [Common Configuration Options](#) chapter. Note, however, that SCS always uses full log message format, regardless of the **message_format** option setting.

alarm

Default Value: No default value

Valid Values (log output types):

stdout	Alarms are sent to the Standard output (stdout).
stderr	Alarms are sent to the Standard error output (stderr).
network	Alarms are sent to Message Server, which resides anywhere on the network, and Message Server stores the log events in the Log Database.
memory	Log events are sent to the memory output on the local disk. This is the safest output in terms of application performance.
[filename]	Alarms are stored to a file with the specified name.
syslog	Alarms are sent to the operating-system log.

Changes Take Effect: Immediately

Specifies to which outputs SCS sends those alarms it generates as a result of appropriate Standard log events. When you configure more than one output type, separate them by a comma. This option is the same as the **alarm** option in [Common Log Options](#) chapter, with the additional value Syslog that is specific to SCS.

Important

For SCS to generate alarms, you must set the **verbose** option to a value other than none.

Example:

To output alarms generated as a result of appropriate Standard log events into the log of the operating system and to a network Message Server, specify **alarm** as the SCS configuration option and Syslog, network as the option value.

eventloghost

Default Value: No default value

Valid Values: Host name

Changes Take Effect: Immediately

Specifies the hostname of the computer whose operating-system log should store Genesys alarm messages. The option works with the **alarm** output level and applies only to computers running Windows NT. If you do not configure this option or do not set its value, alarms are sent to the operating-system log of the computer on which SCS runs.