



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

# Genesys Intelligent Automation Help

Phone Block

# Phone Block



You can use **Phone** blocks to transfer a call to an external phone number or SIP address. The following results are possible:

- **success**
- **no answer**
- **busy**
- **hangup**
- **error**

## Adding this block to the callflow

To add and configure **Phone** blocks on a callflow:

1. Drag and drop the **Phone** block onto the appropriate position in the callflow.
2. Click the **Phone** block to open its properties.
3. In the **Transfer Details** tab:
  - Enter the number to which you want to transfer the caller. You can enter:
    - A phone number.
    - A SIP address (for example, sip:12345@myserver.com).
    - Multiple numbers or SIP addresses, each separated by a comma. The **Phone** block will try each one until it gets an answer or they all fail.
    - A phone number or SIP address in the form of a variable name (for example, [var:MyDestinationNumber]).
  - **Genesys Intelligent Automation validates entered phone numbers to ensure calls are not transferred to any disallowed numbers (for example, premium-rate numbers). Disallowed numbers can be changed by your system administrator.**
  - (Optional) Select the **Use Whisper Transfer** checkbox and configure the prompt you want to play to the agent during a Whisper Transfer. The prompt can include variables, such as [digits:AccountNumber] or [digits:WhisperID]. See the [Whisper Transfer](#) section, below, for more information.
4. (Optional) Apply an [Opening Hours](#) rule to this call to specify at which times and which days calls can be transferred to a specific number. For example, you might not want to transfer to a number during weekends. If a call is made outside of opening hours, a specific prompt plays and the call can transfer to a different phone number or another result as determined by the Opening Hours rule.

### Important

At least one Opening Hours rule must be set up in the current module for the Opening Hours rule list to be visible.


5. Click **Update**.

## Whisper Transfer

This feature allows you to supply the agent with basic details, such as the caller's full name, before the agent speaks to the caller. You can turn on Whisper Transfers for all transfers or for individual transfers.

The agent must provide a DTMF response when provided with the whisper prompt. For example, you might use: Press 1 to accept the call or 2 to decline it. Or, you can add the account number: You have a call from [digits:AccountNumber]. Press 1 to accept or 2 to decline.

If you have provided the **WhisperID** variable as part of the prompt, the agent can use the [CTI Viewer](#) to view the details of the call. For example, you might use: The code is [digits:WhisperID]. Press 1 to accept or 2 to decline.



The following parameters determine the maximum number of times the Whisper Transfer prompt is played to the agent:

- **Maximum no input count** - Defines the maximum number of times a prompt is played to an agent before it times out due to lack of input from the agent.
- **Maximum retry count** - Defines the maximum number of times the retry prompt is played to the agent. The retry prompt may be played to the agent if he or she has selected an invalid option.

If one of these maximums is reached and you still want the call to connect to an agent, you can add the **Connect on whisper transfer timeout** option in the **Preferences** tab. Otherwise, the call returns a **no answer** result.

If the Whisper Transfer is in a queue, you can add the **Two-step whisper transfer** parameter in the **Preferences** tab to specify what happens if the Whisper Transfer is in a queue. When enabled, this parameter plays an introductory message to the agent ("Press **9** to hear the message") in a loop until the agent is ready to hear the actual Whisper Transfer. At this point, the agent can press **9** to hear the message or **8** to reject the call.

### Important

- The maximum number of times the introductory message can be played to the agent is dictated by the length of time specified in the **Transfer timeout** parameter — not the number of iterations. Once the agent presses **9** to hear the actual whisper message, the **Maximum no input count** and **Maximum retry count** parameters determine how many times the message is played.
- By default, Whisper Transfer uses a built-in WAV file (**whispertransfer\_intro.wav**) for the introductory message, but you can override this by uploading a custom prompt named `Standard whisper transfer introduction.wav`.