

GENESYS

This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Genesys Info Mart Operations Guide

Using Genesys Info Mart Manager

Contents

- 1 Using Genesys Info Mart Manager
 - 1.1 Accessing Genesys Info Mart Manager
 - 1.2 How do I view job history?
 - 1.3 How do I start or stop jobs?
 - 1.4 How do I view ETL status?
 - 1.5 How do I see the Genesys Info Mart Manager Help in another language?

Using Genesys Info Mart Manager


The Genesys Info Mart Manager (GIM Manager) provides an interface that you can use to manage Genesys Info Mart jobs.

GIM Manager provides the following views to monitor and manage jobs:

- **Job History** view, where you can view detailed historical information about jobs.
 - Displays the current job execution status.
 - Displays a history of job execution, such as start time, stop time, duration, and final status, and displays detailed information about any delays in processing jobs.
 - Enables you to filter the jobs based on time, status, and other factors.
- ETL Status view, which displays information about latency for each functional area.

The following subsections describe the mechanics of using the GUI. For information about using Genesys Info Mart Manager to manage jobs, see Managing Jobs with Genesys Info Mart Manager.

Accessing Genesys Info Mart Manager



The following brief explanation partially duplicates information from the *Genesys Info Mart Deployment Guide*. For more detailed instructions about accessing Genesys Info Mart Manager, see the Post-Installation Activities in the *Deployment Guide*.

[+] Expand: Prerequisites: Before you can access Genesys Info Mart Manager

To access Genesys Info Mart Manager, ensure that:


- · Genesys Administrator Extension (GAX) and Genesys Info Mart Manager have been installed.
- A Genesys user account with the appropriate permissions and role privileges to access plug-ins and the Genesys Info Mart application has been provisioned. For more information about the required permissions and privileges, see the prerequisites for installing Genesys Info Mart Manager in the Genesys Info Mart Deployment Guide.
- The Genesys Info Mart Server application is started.

To access Genesys Info Mart Manager, use a web browser to log in to GAX, and select **Administration** > **GIM Manager**.

The **GIM Manager** page displays the status of the Genesys Info Mart ETL jobs. If there is more than

one Genesys Info Mart Server in your deployment, use the drop-down list box to choose a server to manage.

How do I view job history?




To filter what jobs appear in the Job History list, you can use either:

1. Quick Filter or 2. Filter

Or use the two tools together for even greater control.

To select what columns appear in the Job History list, click 3. Columns.

To control how often job history and status information is refreshed in the list view, click GIM Manager Settings.



To view detailed information about jobs, click **Job History**. You can customize and filter the display:

To Control What Information is Displayed About Each Job

- To sort the data in the list view, click the column headings. For example, to sort by duration, click the **Duration** column heading. Click again to sort in reverse order.
- To choose what columns appear in the list view, click **Select Columns**. In addition to the default columns, you can, for example, add a column to show the **End Time**, **Job Version**, or **Job ID**.

diT

Changes you make to column visibility and data sort order are not preserved when you reload/refresh the browser page.

To Refresh the Data in the List View

In Genesys Info Mart Manager 8.5.007 and later, Genesys Info Mart Manager automatically refreshes the data in the list view. To enable, disable, or configure this feature, click **GIM Manager Settings**. In the **GIM Manager Settings** dialog, you can configure the following options:

- Enable auto-refresh—Select this option to enable auto-refresh (enabled by default).
- **Auto-refresh frequency**—Enter the number of seconds Genesys Info Mart Manager should wait before refreshing job history and status information. Enter any whole number between 1 and 60; the default is 30 seconds.
- Auto-refresh idle timeout—Enter the number of minutes that Genesys Info Mart Manager can be idle
 before the auto-refresh option is temporarily suspended. Enter any whole number between 1 and 60;
 the default is 30 minutes.

If Genesys Info Mart Manager is inactive for a period of time, the auto-refresh option is temporarily suspended. Click **Refresh List** to resume auto-refresh. You can manually refresh data at any time by clicking **Refresh List**.

Important

In Genesys Info Mart Manager 8.5.004 and earlier, data in the list view is not automatically refreshed. If you are waiting for a job status to change, periodically click **Refresh**.

To Control (filter) What Jobs Appear in the Job History List View

Genesys Info Mart Manager offers two filtering tools: the *Quick Filter* filters the jobs already listed in the Genesys Info Mart Manager view, while the *Filter dialog* retrieves fresh, filtered data from the Genesys Info Mart Server:


- Click **Show Quick Filter** to display the **Quick Filter** field. In the **Quick Filter** field, type one or more characters. As you type, the list of jobs automatically updates to show only those jobs that contain the text you type. This filter checks all visible columns, so you can easily filter by job name, status, duration, job ID, or start/end times. Often a few characters is enough to usefully filter the view; for example, type Ext to show only JobExtractICON jobs.
- Click Filter to open the Filter dialog box. On the Filter dialog box, you can enter a value in the Show
 jobs from this many past days field, which controls how many days' worth of data is displayed. This
 value works in parallel with any one of the following three filtering options:
 - Show a specified number of jobs: Enter the maximum number of jobs to display. For example, enter 10 to display 10 jobs with the most recent start times.
 - Show jobs with a specified status: Select an option from the list to display only jobs that have
 the selected status. For example, select Running to display only jobs that are currently running.
 - **Show all jobs**: Show all jobs from the specified past number of days.

For example, to view all of the jobs that failed in the last week, enter 7 in the **Show jobs from this many past days** field, and select **FAILED** from the **Show jobs with a specified status** list.

Tip

Selections you make in the **Filter** dialog box persist between sessions. Also, the **Quick Filter** and **Filter** features interact with each other. Thus, if you set options in the **Filter** dialog box, you can further refine the filter by entering a value in the **Quick Filter** field.

How do I start or stop jobs?





You can easily start and stop jobs using Genesys Info Mart Manager:

To Start a Job

To start a Genesys Info Mart job:

- 1. Click **Run Job** to open the **Run Job** dialog box.
- 2. On the Run Job dialog box, select a job to run. Job_AggregateGIM can optionally accept parameters

using the **Job Parameters** field; for all other jobs, leave the **Job Parameters** field blank.

3. Click **OK** to start the job.

Note that the job may not run immediately (for example, the job cannot run while other jobs are running). In this case, the status will change to Scheduled, and the job will run as soon as conditions permit.

diT

If you want to stop **Job_AggregateGIM**, you must first ensure that the runaggregates configuration option in the Genesys Info Mart application is set to false.

To Stop a Job

To stop a currently running job, or cancel the **Run Job** command for a job that has not yet started (in other words, a job that has a status of Scheduled), first click **Job History** and select the job, then click **Stop Job**.

The data in the list view is automatically refreshed when you stop a job by clicking **Stop Job**.

To Re-aggregate Data

Run **Job_AggregateGIM**, and in the **Job Parameters** field, enter: -insertPendingAgg <AGR_SET>:<START>:<END> where:


- <AGR_SET> indicates what set to aggregate (ALLSETS, or an aggregate set name). Aggregate set name
 is formatted as follows: <HIERARCHY_NAME>-<AGG_LEVEL>[.Flavor])
 where:
 - <HIERARCHY NAME> is the name of the hierarchy to be aggregated.
 - <AGG LEVEL> is the aggregation level (SUBHOUR, HOUR, DAY, MONTH, QUARTER, YEAR).
 - [.Flavor] indicates what data to include (Online or Offline).
- <START> is a value (YYYY-MM-DD) from the DATE_TIME table that indicates the beginning of the reporting interval.
- <END> is a value (YYYY-MM-DD) from the DATE_TIME table that indicates the end of the reporting interval.

Re-aggregation is possible only if **Job_AggregateGIM** is already running. As a result, if you attempt to pass re-aggregation job parameters when **Job_AggregateGIM** is not running, Genesys Info Mart simply starts aggregation, ignoring the job parameters. In this case, you can re-aggregate by issuing the command to run the job, with the re-aggregation parameters, a second time.

Important

A request to re-aggregate data for a specific time range first deletes aggregated data from that time range (to prevent duplicate data from being written to Info Mart). Before you issue a re-aggregation command, make sure that facts for your selected time range exist in the Info Mart database and have not been purged. Otherwise, you could be left with no aggregates at all for that time range.

How do I view ETL status?



To view information about latency for each functional area, click **ETL Status**.

Latency, which is expressed in the hh:mm:ss format, reflects the time elapsed since the occurrence of the last contact center event for which reporting data has been successfully stored in the Info Mart database. Latency of a few minutes indicates a typical value in a normal operational environment. Immediately after the maintenance job runs, you may notice that latency values are higher than what you usually see for your environment. If there is no activity for a particular data domain over a number of ETL cycles, the latency indicated for that type of data will noticeably increase.

Genesys Info Mart Manager displays the latency for the following functional areas, but only if they are configured on the Genesys Info Mart Server: Extract, Voice Transform, Multimedia Transform, Outbound Contact Transform, Callback

Transform, Media Neutral SM Transform, Elasticsearch, and Aggregation.

In Genesys Info Mart Manager 8.5.004 and earlier, the data displayed represents the status of jobs in the most recent cycle. To display the most recent data at any time, click **Refresh List**.


Functional Area



Sort Order

To sort the data in the list view, click the column headings. For example, to sort by latency, click the **Latency** column heading. Click again to sort in reverse order.

How do I see the Genesys Info Mart Manager Help in another language?



You can select the language used by the GIM Manager GUI. Select the language in the Preferences

menu (click your user name in the menu bar, and choose **System Preferences > Locale** or **User Preferences > Locale**). If the language you want is not listed, see Installing Language Packs for information about how to install localization toolkits for the GIM Manager GUI.
GIM Manager uses the time zone setting, date format, and number format that you select in Genesys Administrator Extension preferences.