



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

SIP Voicemail Deployment Guide

Configuring DNS for the GSVM SIP Server Application

Configuring DNs for the GSVM SIP Server Application

Prerequisites

- The SIP Server Application object dedicated to GSVM is created and associated with the same Switching Office object as the Agent SIP Server Application.

Start

1. Create a Trunk Group DN:
 - a. Under the SIP Server Switch object that is associated with the GSVM SIP Server Application, create a Trunk Group DN. It will be used for the connection with the Resource Manager.
 - b. On the Annex tab, in the TServer section, create the following configuration option:
 - contact: Specify the contact URI of the Resource Manager, in the form of: <ipaddress>:<SIP port>
 - sip-to-pass-through: Set this to true. SIP Server passes the To header (with the mailbox-id) through to Resource Manager without any modifications. GVP resolves the mailbox-id to the correct IVR Profile.

Note: The Complete Install tool creates a default Trunk Group DN 9999. You can use this DN as an example.

- Create a Trunk DN:
 - a. Under the same Switch object, create a Trunk DN object. It will be associated with the Agent SIP Server.
 - b. On the Annex tab, in the TServer section, create the following configuration options:
 - contact: Specify the contact URI of the Agent SIP Server, in the form of: <ipaddress>:<SIP port>
 - force-register: Set this option to the Agent SIP Server voicemail DN, in the form of:

`sip:<voicemail_DN>@<AgentSIP_Server_IP:Port>;user=voicemail`

Note: The Complete Install tool creates a sample Trunk DN Premise-9999. You can use this DN as an example.

End



Return to the [Manual Deployment](#) or [Complete Install](#) task summary.