



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Active Recording Ecosystem Solution Guide

Events and Model Reference

12/13/2025

Events and Model Reference

In addition to capturing the call recording media, recording servers also receive call events from Genesys SIP Server or T-Servers. The [Genesys Events and Models Reference](#) provides a detailed guide on capturing events related to a call or agent events.

There are a few important notes related to multi-site call scenarios to clarify how to reference all call events related to the customer interaction across multiple T-Server instances.

1. The `CallUUID` is a unique call identifier generated on each T-Server instance (or SIP Server instance). When a call is transferred from one T-Server to another, a new `CallUUID` is generated on the other T-Server.
2. The `ConnID` is an identifier assigned to reference a call to initiate requests. In some cases, the `ConnID` is maintained across multi-site transfers. However, the `ConnID` is not guaranteed to be unique across multi-site transfers in some cases.


Genesys offers a mechanism called Inter-Site Link (IS-Link) to build a linked list of call identifiers for the customer interaction across multiple sites. The following is a short overview of how the mechanics work; for full details please refer to the "Multi-Site Call Scenarios" section in the [Genesys Events and Models Reference](#).

When a multi-site call transfer is initiated, it is important to look for the `AttributeISLinkList` attribute provided by the `EventCallDataChanged` event on both of the T-Servers. In order to get call-based events, use the `RequestStartCallMonitoring` event to register for call-based events. When the call is being transferred out of a T-Server, the `EventCallDataChanged` event provides an additional attribute called `AttributeISLinkList`. This is a globally unique identifier that is linked to the destination T-Server. Use this ISLink identifier to locate the `CallUUID` associated with each T-Server instance, so that the entire call can be traced through all transfers across switches.

The `AttributeISLinkList` attribute provides two more keys:

- `location-name`—The switch name of the remote T-Server.
- `direction-role`—Either source or target. If set to source, this T-Server is initiating the transfer. If set to target, this T-Server is receiving the transfer.

ISLink



An example of a call transfer that results in a change of ConnID on T-Server. The ISLink can provide a way to link the CallUUID between different switches.

The call is initially on Tserver2, and transfers the call to SIPServer1.

The EventCallDataChanged event on Tserver2:

```
@09:41:00.5404 [0] 8.1.001.05 distribute call/party event: message EventCallDataChanged
AttributeEventSequenceNumber      0000000000057726
AttributeTimeStamp                 508e957c00083f40
AttributeConnID                   009a021843038407
AttributeCallUUID                  '00RP30KH7088L1IC08GB82LAES000317'
AttributeFirstTransferConnID       009a021843038407
AttributeLastTransferConnID        009a021843038407
AttributeISLinkList                [108] 00 01 03 00..
                                   '00RP30KH7088L1IC08GB82LAES000316' (list) 'location-
name'                               'SIPServer1@SIP_Switch1'
                                   'direction-
role'                               'source'
```

When the call is received on SIPServer1, the EventCallDataChanged shows a common ISLink. This event provides the CallUUID and ConnID for this call on SIPServer1. Note that the ConnID event is common between the two T-Servers at this point.

```
@10:41:00.4955 [0] 8.1.001.03 distribute call/party event: message EventCallDataChanged
AttributeEventSequenceNumber      000000000002d478
AttributeTimeStamp                 508e957c00078fc6
AttributeConnID                   009a021843038407
AttributeCallUUID                  '01AE904GK088LFQD2CGB02LAES0000EP'
AttributeISLinkList                [108] 00 01 03 00..
                                   '00RP30KH7088L1IC08GB82LAES000316' (list) 'location-name'
```

```
'Tserver2@Avaya_Switch1'
role'          'target'          'direction-
```

SIPServer1 then transfers the call back to Tserver2. The EventCallDataChanged event shows the ISLink list as the second item in the list.

```
@10:41:03.5465 [0] 8.1.001.03 distribute call/party event: message EventCallDataChanged
AttributeEventSequenceNumber      000000000002d4c3
AttributeTimeStamp      508e957f000856fe
AttributeConnID          009a021843038407
AttributeCallUUID        '01AE904GK088LFQD2CGB02LAES0000EP'
AttributeISLinkList      [214] 00 02 03 00..
name'          'Tserver2@Avaya_Switch1'
role'          'target'          'direction-
'00EBGH4GK488LFQD2CGB02LAES0007J5'(list) 'location-name'
'Tserver2@Avaya_Switch1'
role'          'source'          'direction-
```

Tserver2 now receives the EventCallDataChanged event with the ISLink. Note that a new CallUUID and ConnID is assigned for this call.

```
@09:41:02.9674 [0] 8.1.001.05 distribute call/party event: message EventCallDataChanged
AttributeEventSequenceNumber      000000000005775c
AttributeTimeStamp      508e957e000ec324
AttributeConnID          009a021843038407
AttributeCallUUID        '00RP30KH7088L1IC08GB82LAES00031D'
AttributeISLinkList      [108] 00 01 03 00..
'SIPServer1@SIP_Switch1'
role'          'target'          'direction-
```