



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

# intelligent Workload Distribution

Genesys Configuration Options Current

# Table of Contents

intelligent Workload Distribution Options Reference	3
iWD Runtime Node Server	4
access-log Section	6
log Section	8
iWD Manager Server	11
oauth Section	13
log Section	15
tomcat Section	18
iWD Section	23
clientApplication Section	26
iWD History Node Server	27
access-log Section	29
log Section	32
iWD Section	36
server Section	39
iWD Web Server	40
security Section	41
boot Section	42
ixn Section	43
Change History	46

# intelligent Workload Distribution Options Reference

Welcome to the Options Reference for intelligent Workload Distribution. This document describes the configuration options for the following components of intelligent Workload Distribution:

- [iWD Runtime Node Server](#)
- [iWD Manager Server](#)
- [iWD History Node Server](#)
- [iWD Web Server](#)

# iWD Runtime Node Server

Options for this component are contained in the following configuration sections:

- [access-log](#)
- [log](#)

## Tip

In the summary table(s) below, type in the Search box to quickly find options, configuration sections, or other values, and/or click a column name to sort the table. Click an option name to link to a full description of the option. Be aware that the default and valid values are the values in effect with the latest release of the software and may have changed since the release you have; refer to the full description of the option to see information for earlier releases.

**Power users:** [Download a CSV file](#) containing default and valid values and descriptions.

The following options are configured at the application level (in other words, on the application object).

Section	Option	Default	Changes Take Effect
access-log	<a href="#">archive</a>	false	After restart
access-log	<a href="#">log-filename</a>	/GCTI/iWD/ iwd_dm_access.log	After restart
access-log	<a href="#">log-to-console</a>	false	After restart
access-log	<a href="#">log-to-file</a>	true	After restart
access-log	<a href="#">max-file-size</a>		After restart
access-log	<a href="#">max-history</a>	5	After restart
access-log	<a href="#">time-zone</a>	UTC	After restart
log	<a href="#">archive</a>	false	After restart
log	<a href="#">centralized-log-level</a>	STANDARD	After restart
log	<a href="#">centralized-logging</a>	false	After restart
log	<a href="#">console-log-level</a>		After restart
log	<a href="#">file-log-level</a>		After restart
log	<a href="#">level</a>	INFO	After restart
log	<a href="#">log-filename</a>	/GCTI/iWD/iwd_dm.log	After restart
log	<a href="#">log-to-console</a>	false	After restart
Section	Option	Default	Changes Take Effect

---

Section	Option	Default	Changes Take Effect
log	log-to-file	true	After restart
log	max-file-size		After restart
log	max-history	5	After restart
log	time-zone	UTC	After restart
Section	Option	Default	Changes Take Effect

## access-log Section

- archive
- log-to-console
- log-to-file
- max-file-size
- max-history
- time-zone

### archive

**Default Value:** false

**Valid Values:** true or false

**Changes Take Effect:** After restart

Determines whether to archive old logs in separate files. Archived filenames are set to <log-filename without extension>-%d-%i<log-filename extension> if file-max-size's set, otherwise: <log-filename without extension>-%d<log-filename extension>

### log-filename

**Default Value:** /GCTI/iWD/iwd\_dm\_access.log

**Valid Values:** Valid file path

**Changes Take Effect:** After restart

The path to log file.

### log-to-console

**Default Value:** false

**Valid Values:** true or false

**Changes Take Effect:** After restart

Determines whether to log to the console.

## log-to-file

**Default Value:** true

**Valid Values:** true or false

**Changes Take Effect:** After restart

Determines whether to log to the file.

## max-file-size

**Default Value:**

**Valid Values:** The value can be expressed in bytes, kilobytes, megabytes or gigabytes by suffixing a numeric value with KB, MB and respectively GB. For example, 5000000, 5000KB, 5MB and 2GB are all valid values, with the first three being equivalent.

**Changes Take Effect:** After restart

Used if archive is true. The maximum size of the currently active file before a rollover is triggered.

## max-history

**Default Value:** 5

**Valid Values:** integer greater than or equal to 0 (zero means to keep infinite number of files)

**Changes Take Effect:** After restart

Used if archive is true. Controls the maximum number of days for archive files to keep, asynchronously deleting older files.

## time-zone

**Default Value:** UTC

**Valid Values:** The ID for a time zone, either an abbreviation such as PST, a full name such as America/Los\_Angeles, or a custom ID such as GMT-8:00.

**Changes Take Effect:** After restart

The time zone to which event timestamps will be converted.

## log Section

- [archive](#)
- [centralized-log-level](#)
- [centralized-logging](#)
- [console-log-level](#)
- [file-log-level](#)
- [level](#)
- [log-filename](#)
- [log-to-console](#)
- [log-to-file](#)
- [max-file-size](#)
- [max-history](#)
- [time-zone](#)

### archive

**Default Value:** false

**Valid Values:** true or false

**Changes Take Effect:** After restart

Determines whether to archive old logs in separate files. Archived filenames are set to <log-filename without extension>-%d-%i<log-filename extension> if file-max-size's set, otherwise: <log-filename without extension>-%d<log-filename extension>

### centralized-log-level

**Default Value:** STANDARD

**Valid Values:** STANDARD, ALARM

**Changes Take Effect:** After restart

Log level of console appender. Centralized appender supports only levels higher than or equal to INFO. STANDARD level corresponds to INFO, so INFO, WARN and ERROR logs will be sent to Message Server, ALARM level corresponds to ERROR log level

### centralized-logging

**Default Value:** false

**Valid Values:** true or false

**Changes Take Effect:** After restart

Determines whether to enable centralized logging.



## console-log-level

**Default Value:**

**Valid Values:** OFF, ERROR, WARN, INFO, DEBUG, TRACE or ALL

**Changes Take Effect:** After restart

Log level of console appender. If not set, logger level is used. Appender level can narrow down logger level but not extend it.

## file-log-level

**Default Value:**

**Valid Values:** OFF, ERROR, WARN, INFO, DEBUG, TRACE or ALL

**Changes Take Effect:** After restart

File appender log level. If not set, logger level is used. Appender level can narrow down logger level but not extend it.

## level

**Default Value:** INFO

**Valid Values:** OFF, ERROR, WARN, INFO, DEBUG, TRACE or ALL

**Changes Take Effect:** After restart

Log level.

## log-filename

**Default Value:** /GCTI/iWD/iwd\_dm.log

**Valid Values:** Valid file path

**Changes Take Effect:** After restart

The path to log file.

## log-to-console

**Default Value:** false

**Valid Values:** true or false

**Changes Take Effect:** After restart

Determines whether to log to the console.

## log-to-file

**Default Value:** true

**Valid Values:** true or false

**Changes Take Effect:** After restart

Determines whether to log to the file.

## max-file-size

**Default Value:**

**Valid Values:** The value can be expressed in bytes, kilobytes, megabytes or gigabytes by suffixing a numeric value with KB, MB and respectively GB. For example, 5000000, 5000KB, 5MB and 2GB are all valid values, with the first three being equivalent.

**Changes Take Effect:** After restart

Used if archive is true. The maximum size of the currently active file before a rollover is triggered.

## max-history

**Default Value:** 5

**Valid Values:** integer greater than or equal to 0 (zero means to keep infinite number of files)

**Changes Take Effect:** After restart

Used if archive is true. Controls the maximum number of days for archive files to keep, asynchronously deleting older files.

## time-zone

**Default Value:** UTC

**Valid Values:** The ID for a time zone, either an abbreviation such as PST, a full name such as America/Los\_Angeles, or a custom ID such as GMT-8:00.

**Changes Take Effect:** After restart

The time zone to which event timestamps will be converted.

# iWD Manager Server

Options for this component are contained in the following configuration sections:

- [clientApplication](#)
- [iWD](#)
- [log](#)
- [oauth](#)
- [tomcat](#)

## Tip

In the summary table(s) below, type in the Search box to quickly find options, configuration sections, or other values, and/or click a column name to sort the table. Click an option name to link to a full description of the option. Be aware that the default and valid values are the values in effect with the latest release of the software and may have changed since the release you have; refer to the full description of the option to see information for earlier releases.

**Power users:** [Download a CSV file](#) containing default and valid values and descriptions.

The following options are configured at the application level (in other words, on the application object).

Section	Option	Default	Changes Take Effect
clientApplication	<a href="#">name</a>		After restart
iWD	<a href="#">cfgConnectionTimeout</a>	60000	After restart
iWD	<a href="#">filterElementValuePattern</a>	(?U)([\\p{Alnum} _%\\.\\- \\]\\p{M})*	After restart
iWD	<a href="#">ixnConnectionTimeout</a>	60000	After restart
iWD	<a href="#">msgConnectionTimeout</a>	60000	After restart
iWD	<a href="#">pullRetryDelayMillis</a>	30	After restart
iWD	<a href="#">pullRetryTimeoutMillis</a>	500	After restart
iWD	<a href="#">queryEscapeCharacter</a>	^	After restart
iWD	<a href="#">taskHistorySizeLimit</a>	5000	After restart
iWD	<a href="#">ucsConnectionTimeout</a>	60000	After restart
log	<a href="#">archive</a>	false	After restart
log	<a href="#">centralized-log-level</a>	STANDARD	After restart
log	<a href="#">centralized-logging</a>	false	After restart
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
log	console-log-level		After restart
log	file-log-level		After restart
log	level	INFO	After restart
log	log-filename	/GCTI/iWD/ iwd_manager.log	After restart
log	log-to-console	false	After restart
log	log-to-file	true	After restart
log	max-file-size		After restart
log	max-history	5	After restart
log	time-zone	UTC	After restart
oauth	base.uri		After restart
oauth	client_id		After restart
oauth	enabled	false	After restart
oauth	password		After restart
oauth	redirect.uri	Empty	After restart
tomcat	accessLogDirectory	/GCTI/iWD	After restart
tomcat	accessLogEnabled	false	After restart
tomcat	accessLogPattern	common	After restart
tomcat	accessLogPrefix	iwd_manager_access	After restart
tomcat	accessLogSuffix	.log	After restart
tomcat	allowBackslash	true	After restart
tomcat	allowEncodedSlash	true	After restart
tomcat	connectionTimeout	60000	After restart
tomcat	contextPath	/iwd_manager	After restart
tomcat	host	0.0.0.0	After restart
tomcat	jsDebugEnabled	false	After restart
tomcat	proxyName	localhost	After restart
tomcat	proxyPort	80	After restart
tomcat	proxySslEnabled	false	After restart
tomcat	proxySupportEnabled	false	After restart
tomcat	relaxedPathChars		After restart
tomcat	relaxedQueryChars		After restart
tomcat	serverName	Apache	After restart
tomcat	sessionTimeout	60	After restart
Section	Option	Default	Changes Take Effect

# oauth Section

- [base.uri](#)
- [client\\_id](#)
- [enabled](#)
- [password](#)
- [redirect.uri](#)

## base.uri

**Default Value:**

**Valid Values:** A fully qualified URI for the OAuth service endpoint; e.g.: <http://localhost:8095/oauth/v3>

**Changes Take Effect:** After restart

Base URI of authorization server that will be accessed during authentication. Locations constructed with this URI will look like: <base\_uri>/oauth/authorize, <base\_uri>/sign-out, etc. Expected format for GWS Auth: <protocol>://<host>:<port>/auth/v3 ; e.g.: <http://localhost:8095/oauth/v3> .

## client\_id

**Default Value:**

**Valid Values:** OAuth2 client ID

**Changes Take Effect:** After restart

Client Identifier required to authenticate IWD manager on authorization server (GWS Auth).

## enabled

**Default Value:** false

**Valid Values:** true or false

**Changes Take Effect:** After restart

Enable OAuth based authentication

## password

**Default Value:**

**Valid Values:** OAuth 2 client secret  
**Changes Take Effect:** After restart

Client Secret required to authenticate IWD manager on authorization server (GWS Auth).

## redirect.uri

**Default Value:** Empty  
**Valid Values:** A fully qualified URI for the iWD Manager endpoint  
**Changes Take Effect:** After restart  
**Discontinued:** 9.0.016.06

After authentication is done, the authorization server redirects users back to iWD Manager using the provided URI.

For example: `http://localhost:8090/iwd_manager`

# log Section

- [archive](#)
- [centralized-log-level](#)
- [centralized-logging](#)
- [console-log-level](#)
- [file-log-level](#)
- [level](#)
- [log-filename](#)
- [log-to-console](#)
- [log-to-file](#)
- [max-file-size](#)
- [max-history](#)
- [time-zone](#)

## archive

**Default Value:** false  
**Valid Values:** true or false  
**Changes Take Effect:** After restart

Determines whether to archive old logs in separate files. Archived filenames are set to <log-filename without extension>-%d-%i<log-filename extension> if file-max-size's set, otherwise: <log-filename without extension>-%d<log-filename extension>

## centralized-log-level

**Default Value:** STANDARD  
**Valid Values:** STANDARD, ALARM  
**Changes Take Effect:** After restart

Log level of console appender. Centralized appender supports only levels higher than or equal to INFO. STANDARD level corresponds to INFO, so INFO, WARN and ERROR logs will be sent to Message Server, ALARM level corresponds to ERROR log level

## centralized-logging

**Default Value:** false  
**Valid Values:** true or false  
**Changes Take Effect:** After restart

Determines whether to enable centralized logging.

---

## console-log-level

**Default Value:**

**Valid Values:** OFF, ERROR, WARN, INFO, DEBUG, TRACE or ALL

**Changes Take Effect:** After restart

Log level of console appender. If not set, logger level is used. Appender level can narrow down logger level but not extend it.

## file-log-level

**Default Value:**

**Valid Values:** OFF, ERROR, WARN, INFO, DEBUG, TRACE or ALL

**Changes Take Effect:** After restart

File appender log level. If not set, logger level is used. Appender level can narrow down logger level but not extend it.

## level

**Default Value:** INFO

**Valid Values:** OFF, ERROR, WARN, INFO, DEBUG, TRACE or ALL

**Changes Take Effect:** After restart

Log level.

## log-filename

**Default Value:** /GCTI/iWD/iwd\_manager.log

**Valid Values:** Valid file path

**Changes Take Effect:** After restart

The path to log file.

## log-to-console

**Default Value:** false

**Valid Values:** true or false

**Changes Take Effect:** After restart

Determines whether to log to the console.



---

## log-to-file

**Default Value:** true

**Valid Values:** true or false

**Changes Take Effect:** After restart

Determines whether to log to the file.

## max-file-size

**Default Value:**

**Valid Values:** The value can be expressed in bytes, kilobytes, megabytes or gigabytes by suffixing a numeric value with KB, MB and respectively GB. For example, 5000000, 5000KB, 5MB and 2GB are all valid values, with the first three being equivalent.

**Changes Take Effect:** After restart

Used if archive is true. The maximum size of the currently active file before a rollover is triggered.

## max-history

**Default Value:** 5

**Valid Values:** integer greater than or equal to 0 (zero means to keep infinite number of files)

**Changes Take Effect:** After restart

Used if archive is true. Controls the maximum number of days for archive files to keep, asynchronously deleting older files.

## time-zone

**Default Value:** UTC

**Valid Values:** The ID for a time zone, either an abbreviation such as PST, a full name such as America/Los\_Angeles, or a custom ID such as GMT-8:00.

**Changes Take Effect:** After restart

The time zone to which event timestamps will be converted.

## tomcat Section

- `accessLogDirectory`
- `accessLogEnabled`
- `accessLogPattern`
- `accessLogPrefix`
- `accessLogSuffix`
- `allowBackslash`
- `allowEncodedSlash`
- `connectionTimeout`
- `contextPath`
- `host`
- `jsDebugEnabled`
- `proxyName`
- `proxyPort`
- `proxySslEnabled`
- `proxySupportEnabled`
- `relaxedPathChars`
- `relaxedQueryChars`
- `serverName`
- `sessionTimeout`

### accessLogDirectory

**Default Value:** `/GCTI/iWD`  
**Valid Values:** Valid path to directory  
**Changes Take Effect:** After restart

Absolute or relative pathname of a directory in which access log files will be placed. If a relative path is specified, it is interpreted as relative to `$CATALINA_BASE`

### accessLogEnabled

**Default Value:** `false`  
**Valid Values:** `true` or `false`  
**Changes Take Effect:** After restart

Enables access logging

### accessLogPattern

**Default Value:** `common`  
**Valid Values:** Valid pattern code  
**Changes Take Effect:** After restart

A formatting layout identifying the various information fields from the request and response to be logged, or the word common or combined to select a standard format. Supported pattern codes are described on [https://tomcat.apache.org/tomcat-8.5-doc/config/valve.html#Access\\_Log\\_Valve](https://tomcat.apache.org/tomcat-8.5-doc/config/valve.html#Access_Log_Valve)

## accessLogPrefix

**Default Value:** iwd\_manager\_access  
**Valid Values:** Valid prefix for filename  
**Changes Take Effect:** After restart

The prefix added to the start of each log file's name.

## accessLogSuffix

**Default Value:** .log  
**Valid Values:** Valid suffix for filename  
**Changes Take Effect:** After restart

The suffix added to the end of each log file's name.

## allowBackslash

**Default Value:** true  
**Valid Values:** true or false  
**Changes Take Effect:** After restart

Allow encoded backslash in url.

## allowEncodedSlash

**Default Value:** true  
**Valid Values:** true or false  
**Changes Take Effect:** After restart

Allow encoded slash in url.

## connectionTimeout

**Default Value:** 60000  
**Valid Values:** Any integer from 0-86400000  
**Changes Take Effect:** After restart

The number of milliseconds this Connector will wait, after accepting a connection, for the request URI line to be presented. Use a value of -1 to indicate no (i.e. infinite) timeout

## contextPath

**Default Value:** /iwd\_manager  
**Valid Values:** The valid context path  
**Changes Take Effect:** After restart

Application context path.

## host

**Default Value:** 0.0.0.0  
**Valid Values:** The valid host  
**Changes Take Effect:** After restart

The host can either be a machine name or a textual representation of its IP address. Setting the host to 0.0.0.0 indicates that Server will be listening on all interfaces.

## jsDebugEnabled

**Default Value:** false  
**Valid Values:** true or false  
**Changes Take Effect:** After restart

Enables JavaScript debugging

## proxyName

**Default Value:** localhost  
**Valid Values:** Valid server name  
**Changes Take Effect:** After restart

Proxy server name

## proxyPort

**Default Value:** 80  
**Valid Values:** Any integer from 1-65535  
**Changes Take Effect:** After restart

Proxy server port

## proxySslEnabled

**Default Value:** false

**Valid Values:** true or false

**Changes Take Effect:** After restart

Indicates if proxy has SSL enabled

## proxySupportEnabled

**Default Value:** false

**Valid Values:** true or false

**Changes Take Effect:** After restart

Enables Proxy Support

## relaxedPathChars

**Default Value:**

**Valid Values:**

**Changes Take Effect:** After restart

Allows provided chars to be used in url path

## relaxedQueryChars

**Default Value:**

**Valid Values:**

**Changes Take Effect:** After restart

Allows provided chars to be used in url query

## serverName

**Default Value:** Apache

**Valid Values:** The valid server name

**Changes Take Effect:** After restart

Server name in response header

## sessionTimeout

**Default Value:** 60

**Valid Values:** Any integer from 0-1440

**Changes Take Effect:** After restart

Set the default session timeout (in minutes) for this web application

## iWD Section

- `cfgConnectionTimeout`
- `filterElementValuePattern`
- `ixnConnectionTimeout`
- `msgConnectionTimeout`
- `pullRetryDelayMillis`
- `pullRetryTimeoutMillis`
- `queryEscapeCharacter`
- `taskHistorySizeLimit`
- `ucsConnectionTimeout`

### cfgConnectionTimeout

**Default Value:** 60000  
**Valid Values:** Any integer from 0-86400000  
**Changes Take Effect:** After restart

Connection to Config Server timeout in milliseconds.

### filterElementValuePattern

**Default Value:** `(?U)([\p{Alnum} _%.\-\\]\p{M})*`  
**Valid Values:** Valid Java compatible regular expression  
**Changes Take Effect:** After restart

Allowed values in GTL filter criteria. The syntax has to be compatible with Java regular expressions (<https://docs.oracle.com/javase/8/docs/api/java/util/regex/Pattern.html>). Default for Unicode: a sequence of (alphabetic or digit or space or dot or minus, followed by zero or more modifiers). The characters ' (apostrophe) and " (quotation) are forbidden internally in stored filters, regardless of this pattern. They may be allowed in quick (ad hoc) filters.

### ixnConnectionTimeout

**Default Value:** 60000  
**Valid Values:** Any integer from 0-86400000  
**Changes Take Effect:** After restart

Connection to Interaction Server timeout in milliseconds.

---

---

## msgConnectionTimeout

**Default Value:** 60000  
**Valid Values:** Any integer from 0-86400000  
**Changes Take Effect:** After restart

Connection to Message Server timeout in milliseconds.

## pullRetryDelayMillis

**Default Value:** 30  
**Valid Values:** Any integer from 0-86400000  
**Changes Take Effect:** After restart

When a request to "pull" an interaction from Interaction Server fails, it will be automatically repeated after some time of waiting. Time of waiting before each attempt.

## pullRetryTimeoutMillis

**Default Value:** 500  
**Valid Values:** Any integer from 0-86400000  
**Changes Take Effect:** After restart

When a request to "pull" an interaction from Interaction Server fails, it will be automatically repeated after some time of waiting. Maximum time of trying to pull an interaction (in milliseconds).

## queryEscapeCharacter

**Default Value:** ^  
**Valid Values:** Any character supported by the database  
**Changes Take Effect:** After restart  
**Introduced:** 9.0.012

The escape character instructs the LIKE operator to treat the wildcard characters as the regular characters. It is used in custom QL filter.

## taskHistorySizeLimit

**Default Value:** 5000  
**Valid Values:** Any integer from 1-500000  
**Changes Take Effect:** After restart

Maximum number of events to display in Task History



## ucsConnectionTimeout

**Default Value:** 60000

**Valid Values:** Any integer from 0-86400000

**Changes Take Effect:** After restart

Connection to UCS timeout in milliseconds.

## clientApplication Section

- **name**

### name

**Default Value:**

**Valid Values:** The valid name of client application

**Changes Take Effect:** After restart

iWD Manager requires additional application to initiate connections after user login.

Provide the client application name

# iWD History Node Server

Options for this component are contained in the following configuration sections:

- [access-log](#)
- [iWD](#)
- [log](#)
- [server](#)

## Tip

In the summary table(s) below, type in the Search box to quickly find options, configuration sections, or other values, and/or click a column name to sort the table. Click an option name to link to a full description of the option. Be aware that the default and valid values are the values in effect with the latest release of the software and may have changed since the release you have; refer to the full description of the option to see information for earlier releases.

**Power users:** [Download a CSV file](#) containing default and valid values and descriptions.

The following options are configured at the application level (in other words, on the application object).

Section	Option	Default	Changes Take Effect
access-log	<a href="#">archive</a>	false	After restart
access-log	<a href="#">archived-file-count</a>	5	After restart
access-log	<a href="#">archived-log-filename-pattern</a>		After restart
access-log	<a href="#">log-filename</a>	/GCTI/iWD/iwd_history_access.log	After restart
access-log	<a href="#">log-to-console</a>	false	After restart
access-log	<a href="#">log-to-file</a>	true	After restart
access-log	<a href="#">max-file-size</a>		After restart
access-log	<a href="#">max-history</a>	5	After restart
access-log	<a href="#">time-zone</a>	UTC	After restart
iWD	<a href="#">allow-listed-attributes</a>		After restart
iWD	<a href="#">batch-size</a>	1000	After restart
iWD	<a href="#">block-listed-attributes</a>		After restart
iWD	<a href="#">migrate-schema</a>	false	After restart
iWD	<a href="#">process-dm</a>	true	After restart
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
iWD	process-gtl	true	After restart
iWD	processor-threads	10	After restart
iWD	receive-timeout	10	After restart
iWD	stop-processing	remove	After restart
iWD	stop-processing-delay	60	After restart
iWD	stop-processing-interval	60	After restart
iWD	taskEventLimit		After restart
log	archive	false	After restart
log	archived-file-count	5	After restart
log	archived-log-filename-pattern		After restart
log	centralized-log-level	STANDARD	After restart
log	centralized-logging	false	After restart
log	console-log-level		After restart
log	file-log-level		After restart
log	level	INFO	After restart
log	log-filename	/GCTI/iWD/iwd_history.log	After restart
log	log-to-console	false	After restart
log	log-to-file	true	After restart
log	max-file-size		After restart
log	max-history	5	After restart
log	time-zone	UTC	After restart
server	single-host-bind	false	After restart
Section	Option	Default	Changes Take Effect

## access-log Section

- `archive`
- `archive-file-count`
- `archive-log-filename-pattern`
- `log-filename`
- `log-to-console`
- `log-to-file`
- `max-file-size`
- `max-history`
- `time-zone`

### archive

**Default Value:** false

**Valid Values:** true or false

**Changes Take Effect:** After restart

Determines whether to archive old logs in separate files. Archived filenames are set to `<log-filename without extension>-%d-%i<log-filename extension>` if `file-max-size`'s set, otherwise: `<log-filename without extension>-%d<log-filename extension>`

### archive-file-count

**Default Value:** 5

**Valid Values:** Any nonnegative integer

**Changes Take Effect:** After restart

The number of archived files to keep. Value 0 indicates an infinite number.

### archive-log-filename-pattern

**Default Value:**

**Valid Values:** Valid filename pattern

**Changes Take Effect:** After restart

The filename pattern for archived access log files. Required if the value of **archive** is true. If **max-file-size** is specified, rollover is size-based, and the pattern must contain `%i` for an integer index of the archived file. Otherwise rollover is date-based, and the pattern must contain `%d`, which is replaced with the date in `yyyy-MM-dd` form. If the pattern ends with `.gz` or `.zip`, files will be compressed as they are archived.

## log-filename

**Default Value:** /GCTI/iWD/iwd\_history\_access.log

**Valid Values:** Valid file path

**Changes Take Effect:** After restart

The path to log file.

## log-to-console

**Default Value:** false

**Valid Values:** true or false

**Changes Take Effect:** After restart

Determines whether to log to the console.

## log-to-file

**Default Value:** true

**Valid Values:** true or false

**Changes Take Effect:** After restart

Determines whether to log to the file.

## max-file-size

**Default Value:**

**Valid Values:** The value can be expressed in bytes, kilobytes, megabytes or gigabytes by suffixing a numeric value with KB, MB and respectively GB. For example, 5000000, 5000KB, 5MB and 2GB are all valid values, with the first three being equivalent.

**Changes Take Effect:** After restart

Used if archive is true. The maximum size of the currently active file before a rollover is triggered.

## max-history

**Default Value:** 5

**Valid Values:** integer greater than or equal to 0 (zero means to keep infinite number of files)

**Changes Take Effect:** After restart

Used if archive is true. Controls the maximum number of days for archive files to keep,

---

asynchronously deleting older files.

## time-zone

**Default Value:** UTC

**Valid Values:** The ID for a time zone, either an abbreviation such as PST, a full name such as America/Los\_Angeles, or a custom ID such as GMT-8:00.

**Changes Take Effect:** After restart

The time zone to which event timestamps will be converted.

# log Section

- `archive`
- `archive-file-count`
- `archive-log-filename-pattern`
- `centralized-log-level`
- `centralized-logging`
- `console-log-level`
- `file-log-level`
- `level`
- `log-filename`
- `log-to-console`
- `log-to-file`
- `max-file-size`
- `max-history`
- `time-zone`

## archive

**Default Value:** false

**Valid Values:** true or false

**Changes Take Effect:** After restart

Determines whether to archive old logs in separate files. Archived filenames are set to `<log-filename without extension>-%d-%i<log-filename extension>` if `file-max-size`'s set, otherwise: `<log-filename without extension>-%d<log-filename extension>`

## archive-file-count

**Default Value:** 5

**Valid Values:** Any nonnegative integer

**Changes Take Effect:** After restart

The number of archived files to keep. Value 0 means an infinite number of files.

## archive-log-filename-pattern

**Default Value:**

**Valid Values:** Valid filename pattern

**Changes Take Effect:** After restart

The filename pattern for archived files. Required if the value of `archive` is true. If `max-file-size` is specified, rollover is size-based, and the pattern must contain `%i` for an integer index of the archived



file. Otherwise rollover is date-based, and the pattern must contain %d, which is replaced with the date in yyyy-MM-dd form. If the pattern ends with .gz or .zip, files will be compressed as they are archived.

## centralized-log-level

**Default Value:** STANDARD  
**Valid Values:** STANDARD, ALARM  
**Changes Take Effect:** After restart

Log level of console appender. Centralized appender supports only levels higher than or equal to INFO. STANDARD level corresponds to INFO, so INFO, WARN and ERROR logs will be sent to Message Server, ALARM level corresponds to ERROR log level

## centralized-logging

**Default Value:** false  
**Valid Values:** true or false  
**Changes Take Effect:** After restart

Determines whether to enable centralized logging.

## console-log-level

**Default Value:**  
**Valid Values:** OFF, ERROR, WARN, INFO, DEBUG, TRACE or ALL  
**Changes Take Effect:** After restart

Log level of console appender. If not set, logger level is used. Appender level can narrow down logger level but not extend it.

## file-log-level

**Default Value:**  
**Valid Values:** OFF, ERROR, WARN, INFO, DEBUG, TRACE or ALL  
**Changes Take Effect:** After restart

File appender log level. If not set, logger level is used. Appender level can narrow down logger level but not extend it.

## level

**Default Value:** INFO

**Valid Values:** OFF, ERROR, WARN, INFO, DEBUG, TRACE or ALL

**Changes Take Effect:** After restart

Log level.

## log-filename

**Default Value:** /GCTI/iWD/iwd\_history.log

**Valid Values:** Valid file path

**Changes Take Effect:** After restart

The path to log file.

## log-to-console

**Default Value:** false

**Valid Values:** true or false

**Changes Take Effect:** After restart

Determines whether to log to the console.

## log-to-file

**Default Value:** true

**Valid Values:** true or false

**Changes Take Effect:** After restart

Determines whether to log to the file.

## max-file-size

**Default Value:**

**Valid Values:** The value can be expressed in bytes, kilobytes, megabytes or gigabytes by suffixing a numeric value with KB, MB and respectively GB. For example, 5000000, 5000KB, 5MB and 2GB are all valid values, with the first three being equivalent.

**Changes Take Effect:** After restart

Used if archive is true. The maximum size of the currently active file before a rollover is triggered.

## max-history

**Default Value:** 5

**Valid Values:** integer greater than or equal to 0 (zero means to keep infinite number of files)

**Changes Take Effect:** After restart

Used if archive is true. Controls the maximum number of days for archive files to keep, asynchronously deleting older files.

## time-zone

**Default Value:** UTC

**Valid Values:** The ID for a time zone, either an abbreviation such as PST, a full name such as America/Los\_Angeles, or a custom ID such as GMT-8:00.

**Changes Take Effect:** After restart

The time zone to which event timestamps will be converted.

## iWD Section

- `allow-listed-attributes`
- `batch-size`
- `block-listed-attributes`
- `migrate-schema`
- `process-dm`
- `process-gtl`
- `processor-threads`
- `receive-timeout`
- `stop-processing`
- `stop-processing-delay`
- `stop-processing-interval`
- `taskEventLimit`

### allow-listed-attributes

**Default Value:**

**Valid Values:** Comma separated list of attributes

**Changes Take Effect:** After restart

**Introduced:** 9.0.016.09

Specifies the (comma-separated) list of attributes to be shown in global task list history. For example, specific desired system-generated or strategy-generated attributes. You can specify `_ALL_` keyword to allow all attributes.

### batch-size

**Default Value:** 1000

**Valid Values:** Valid number of events

**Changes Take Effect:** After restart

Maximum number of events which will be saved at once in history DB. Note: one event may translate to multiple rows in the database.

### block-listed-attributes

**Default Value:**

**Valid Values:** Comma separated list of attributes

**Changes Take Effect:** After restart

**Introduced:** 9.0.016.09

Specifies the (comma-separated) list of attributes to be filtered out of global task list history. For example, unwanted system-generated or strategy-generated attributes. You can specify `_ALL_` keyword to block all attributes except listed in the `allow-listed-attributes` list.

## migrate-schema

**Default Value:** false  
**Valid Values:** true or false  
**Changes Take Effect:** After restart

Determines whether database schema should be migrated (i.e. updated) during application start.

## process-dm

**Default Value:** true  
**Valid Values:** true or false  
**Changes Take Effect:** After restart

Determines whether datamart events should be processed and saved in history DB.

## process-gtl

**Default Value:** true  
**Valid Values:** true or false  
**Changes Take Effect:** After restart

Determines whether GTL history events should be processed and saved in history DB.

## processor-threads

**Default Value:** 10  
**Valid Values:** Valid number of processor threads  
**Changes Take Effect:** After restart

Number of processor threads used for events processing.

## receive-timeout

**Default Value:** 10  
**Valid Values:** Valid number of milliseconds  
**Changes Take Effect:** After restart

Number of milliseconds since last event received from JMS queue after which cached events will be flushed to the history DB.

## stop-processing

**Default Value:** remove

**Valid Values:** Keep or remove

**Changes Take Effect:** After restart

History Node behavior after receiving "Stop processing" event from Interaction Server. If "keep", interaction history will be preserved; if "remove", interaction history will be purged after specified timeout.

## stop-processing-delay

**Default Value:** 60

**Valid Values:** Valid number of seconds

**Changes Take Effect:** After restart

Number of seconds since stop processing event received from JMS queue after which interaction history will be purged from database.

## stop-processing-interval

**Default Value:** 60

**Valid Values:** Valid number of seconds

**Changes Take Effect:** After restart

Frequency of history purge in seconds.

## taskEventLimit

**Default Value:**

**Valid Values:** Any positive integer

**Changes Take Effect:** After restart

**Introduced:** 9.0.013.11

The maximum number of events that will be migrated from the Events Log database. If the parameter is not defined or it is set to 0 (zero) the migration process will try to process all existing events of Events Log database.

## server Section

- `single-host-bind`

### single-host-bind

**Default Value:** false

**Valid Values:** Listen to single or all addresses

**Changes Take Effect:** After restart

Determines on which address History Node will be listening. If true, History Node only listens to address specified in Server Info; if false, History Node listens to all available addresses on the machine (0.0.0.0).

# iWD Web Server

Options for this component are contained in the following configuration sections:

- [boot](#)
- [ixn](#)
- [security](#)

## Tip

In the summary table(s) below, type in the Search box to quickly find options, configuration sections, or other values, and/or click a column name to sort the table. Click an option name to link to a full description of the option. Be aware that the default and valid values are the values in effect with the latest release of the software and may have changed since the release you have; refer to the full description of the option to see information for earlier releases.

**Power users:** [Download a CSV file](#) containing default and valid values and descriptions.

The following options are configured at the application level (in other words, on the application object).

Section	Option	Default	Changes Take Effect
boot	<a href="#">iwdweb.config_server.client_app_name</a>		After restart
ixn	<a href="#">capture_point_id</a>		After restart
ixn	<a href="#">default_media_type</a>	workitem	After restart
ixn	<a href="#">department_id</a>		After restart
ixn	<a href="#">interaction_subtype</a>	InboundNew	After restart
ixn	<a href="#">interaction_type</a>	Inbound	After restart
ixn	<a href="#">priority</a>	2	After restart
ixn	<a href="#">process_id</a>		After restart
ixn	<a href="#">request_submit_timeout</a>	10	After restart
ixn	<a href="#">solution_id</a>		After restart
security	<a href="#">iwdweb.tls.keyStore</a>		After restart
security	<a href="#">iwdweb.tls.keyStorePassword</a>		After restart
security	<a href="#">iwdweb.tls.validateCert</a>	off	After restart
Section	Option	Default	Changes Take Effect



## security Section

- [iwdweb.tls.keyStore](#)
- [iwdweb.tls.keyStorePassword](#)
- [iwdweb.tls.validateCert](#)

### iwdweb.tls.keyStore

**Default Value:**

**Valid Values:** The valid path to key storage

**Changes Take Effect:** After restart

Path to the TLS key store.

### iwdweb.tls.keyStorePassword

**Default Value:**

**Valid Values:** The valid password to key storage

**Changes Take Effect:** After restart

TLS key store password.

### iwdweb.tls.validateCert

**Default Value:** off

**Valid Values:** on, off

**Changes Take Effect:** After restart

Always validate certificate. With value off, certificate is not being validated.

## boot Section

- `ibdweb.config_server.client_app_name`

### `ibdweb.config_server.client_app_name`

**Default Value:**

**Valid Values:** The valid name of client application

**Changes Take Effect:** After restart

iWDWeb requires additional application to initiate connections after user login.

Provide the client application name

## ixn Section

- `capture_point_id`
- `default_media_type`
- `department_id`
- `interaction_subtype`
- `interaction_type`
- `priority`
- `process_id`
- `request_submit_timeout`
- `solution_id`

### capture\_point\_id

**Default Value:****Valid Values:** The valid name of capture point identifier**Changes Take Effect:** After restart

iWDWeb requires a capture point identifier used to submit interaction to Interaction Server.

Provide the capture point identifier

### default\_media\_type

**Default Value:** workitem**Valid Values:** The valid name of media type**Changes Take Effect:** After restart

iWDWeb requires a media type of interaction used to submit it to Interaction Server.

Provide the media type

### department\_id

**Default Value:****Valid Values:** The valid name of department identifier**Changes Take Effect:** After restart

iWDWeb requires a department identifier used to submit interaction to Interaction Server.

Provide the department identifier

## interaction\_subtype

**Default Value:** InboundNew

**Valid Values:** The valid name of interaction subtype from Interaction Subtype Business Attribute

**Changes Take Effect:** After restart

A subtype of interaction used in submit it to Interaction Server.

Provide the interaction subtype

## interaction\_type

**Default Value:** Inbound

**Valid Values:** The valid name of interaction type from Interaction Type Business Attribute

**Changes Take Effect:** After restart

A type of interaction used in submit it to Interaction Server.

Provide the interaction type

## priority

**Default Value:** 2

**Valid Values:** The value of priority

**Changes Take Effect:** After restart

An interaction priority used to submit it to Interaction Server.

Provide the interaction priority

## process\_id

**Default Value:**

**Valid Values:** The valid name of process identifier

**Changes Take Effect:** After restart

iWDWeb requires a process identifier used to submit interaction to Interaction Server.

Provide the process identifier

## request\_submit\_timeout

**Default Value:** 10

**Valid Values:** The value of submit protocol timeout

**Changes Take Effect:** After restart

Protocol timeout value for submit interaction to Interaction Server.

Provide the submit protocol timeout

## solution\_id

**Default Value:**

**Valid Values:** The valid name of solution identifier

**Changes Take Effect:** After restart

iWDWeb requires a solution identifier used to submit interaction to Interaction Server.

Provide the solution identifier

# Change History

Content under development