



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Skype for Business

startup Section

12/20/2025

startup Section

- application-port
- application-urn
- application-user-agent
- certificate-thumbprint
- computer-gruu
- persistent-storage-path
- provision-mode
- server-address
- server-port

application-port

Default Value: 0

Valid Values: Any positive integer

Changes Take Effect: Startup only

The configured port of Trusted Application to listen to incoming connections—for example: 6001. Mandatory when **provision-mode**=manual.

application-urn

Default Value: No default value

Valid Values: Any application URN defined in the configuration

Changes Take Effect: After restart

Specifies the unique identifier of the application in the deployment. It is assigned when the application is provisioned.

Example: urn:application:Connector_app

Mandatory—must be specified.

application-user-agent

Default Value: Genesys SfB Connector

Valid Values: Any string

Changes Take Effect: Startup only

The part of the user agent string that identifies the application. Can be empty or non-present.

certificate-thumbprint

Default Value: No default value

Valid Values: Thumbprint of existing certificate

Changes Take Effect: Startup only

The thumbprint of the certificate to use for Trusted Application.
Mandatory when **provision-mode**=manual.

computer-gruu

Default Value: No default value

Valid Values: computerGRUU from Skype for Business configuration

Changes Take Effect: Startup only

Computer GRUU of Trusted Application. The value is unique for each Connector.

Example:

sip:computer1.lyncdco.lab@lyncdco.lab;gruu;opaque=srvr:connector_app:qFBsnVw_QV-oZ_uG-ia3xAAA

Mandatory when **provision-mode**=manual.

persistent-storage-path

Default Value: No default value

Valid Values: absolute or relative path to existing directory

Changes Take Effect: Startup only

Specifies a directory where Connector creates a persistent file that contains information about the statuses of all conferences scheduled by Connector.

provision-mode

Default Value: manual

Valid Values: auto, manual

Changes Take Effect: Startup only

Introduced: 9.0.000.xx

Defines the provisioning mode the Connector will use for communication with the Skype for Business Server:

- auto—Auto-provisioning mode of work is used.
- manual—Manual provisioning mode of work is used.

For more information about auto-provisioning mode, see Microsoft documentation.

server-address

Default Value:

Valid Values: Any string

Changes Take Effect: After restart

The FQDN of FrontEnd of Skype for Business Server for the UCMA application connection. Example: pool01.lyncdco.lab

server-port

Default Value: 5061

Valid Values: TCP/IP port

Changes Take Effect: Startup only

The port of the FrontEnd pool of Skype for Business for the UCMA application connection. Example: 5061