



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Log File Management Tool Deployment and User's Guide

LFMT Indexer Configuration Options

Contents

- 1 LFMT Indexer Configuration Options
 - 1.1 app_config Section
 - 1.2 log Section
 - 1.3 thread_setting Section

LFMT Indexer Configuration Options

This section contains options used to configure the LFMT Indexer.

Unless otherwise stated, all configuration options are set using GAX in the **Application Options** tab of the **LFMT Indexer** object.

Examples:

Name	Section	Key	Value
app_config			
app_config \ app_type	app_config	app_type	indexer
app_config \ cls_location	app_config	cls_location	/home/genesys/gcti/LFMT_CLS
app_config \ retention_period	app_config	retention_period	14
log			
log \ all	log	all	/home/genesys/_logs/LFMT_Indexer/LFMT_Indexer
log \ expire	log	expire	20
log \ segment	log	segment	20MB
log \ verbose	log	verbose	all
thread_setting			
thread_setting \ max_queue	thread_setting	max_queue	40
thread_setting \ max_threads	thread_setting	max_threads	40
thread_setting \ min_threads	thread_setting	min_threads	20

app_config Section

This section contains options for general configuration of the LFMT Indexer application; this section must be called **app_config**.

app_type

Default Value: indexer

Valid Values: indexer

Changes Take Effect: After restart of LFMT Indexer.

Description: Specifies the type of Generic Genesys Server this application represents.

cls_location

Default Value: **No default value - please enter a value here**

Valid Values: Valid path through the system (i.e. **C:\CLS** or **/home/genesys/gcti/LFMT_CLS**)

Changes Take Effect: After restart of LFMT Indexer.

Description: Specifies the path (local to Collector Host and **not** a mapped network drive) through the system to the folder or directory where the CLS is located; for example, C : /GCTI/CLS.

Important

- Please ensure this option is set with a valid path, and the user has write permissions to the path, before starting the LFMT Indexer(s) application

retention_period

Default Value: **3**

Valid Values: Any positive integer

Changes Take Effect: After restart of LFMT Indexer.

Description: Specifies the number of days that the unmodified files are stored in CLS before they are deleted permanently; this value **should be greater than or equal** to the value of the **LFMT Collector** application **collection_period** option.

log Section

This section contains all options relating to creating, viewing, and otherwise using the Centralized Log facility in Genesys software; this section must be called **log**.

all

Default value: No default value

Valid Values: **[path/filename]** (i.e. **/home/genesys/gcti/_logs/LFMT_Indexer/LFMT_Indexer**)

Changes Take Effect: After restart of LFMT Indexer.

Description: Specifies the file location to which the application sends all log events.

expire

Default value: **10**

Valid Values: [number] Specify a number from 1-1000.

Changes Take Effect: After restart of LFMT Indexer.

Description: Determines how many log files are kept before they are deleted.

segment

Default value: **5000**

Valid Values: [number] - Specify a value in kilobytes.
Changes Take Effect: After restart of LFMT Indexer.
Description: Determines the rollover size of the log files.

verbose

Default value: **all**
Valid Values:

- **all** - All log events are printed.
- **trace** - All log events are printed.
- **debug** - DEBUG, INFO, WARN, FATAL, and ERROR log events are printed.
- **info** - INFO, WARN, FATAL, and ERROR log events are printed.
- **warn** - WARN, FATAL, and ERROR log events are printed.
- **error** - FATAL and ERROR log events are printed.
- **fatal** - Only FATAL log events are printed.
- **off** - No log events are printed.

Changes Take Effect: After restart of LFMT Indexer.
Description: Specifies the log level.

thread_setting Section

This section defines the number of threads required for the indexed to process files in parallel; this section must be called **thread_setting**.

max_queue

Default value: **40**
Valid Values: Any integer
Changes Take Effect: After restart of LFMT Indexer.
Description: Specifies the number of files to keep in the queue when all the threads are busy before the indexer starts generating exceptions.

max_threads

Default value: **40**
Valid Values: Any integer
Changes Take Effect: After restart of LFMT Indexer.
Description: Specifies the maximum number of threads required to process the files in parallel.

min_threads

Default value: **20**
Valid Values: Any integer

Changes Take Effect: After restart of LFMT Indexer.

Description: Specifies the minimum number of threads required to process files in parallel.