



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Framework Database Connectivity Guide

Oracle Databases

9/5/2025

Oracle Databases

Contents

- 1 Oracle Databases
 - 1.1 Using Full Installation of Oracle Client
 - 1.2 Using Oracle Instant Client
 - 1.3 Using Oracle Database with National Languages
 - 1.4 Using Oracle TAF
 - 1.5 Failure of an Oracle 12g RAC Database

You must have Oracle Client software accessible in the environment where the Genesys application is running. Genesys uses Oracle 11g client software to access all supported versions of Oracle.

Using Full Installation of Oracle Client

Connectivity to an Oracle database relies on TCP/IP to work between an Oracle server and its client.

You must set the following environment variables for DB client for Oracle:

ORACLE_HOME
ORACLE_SID

In addition, you must specify the full path to the **bin** of the Oracle home directory in the **PATH** variable, and either **LIBPATH** for AIX or **LD_LIBRARY_PATH** for Linux and Solaris, depending on the platform you are using. If the DBMS client for Oracle runs on a different host other than the Oracle server, you must also configure the **SQLNet** file on both hosts. Note that a TCP/IP Adapter is also required. For more information, refer to the Oracle documentation for your platform.

If you are using the UNIX/Linux platform, you might want to create a link to the DB client so that the server accessing the database can find the library using the default name. Enter the following on the operating system command line:

```
ln -s libclntsh.so.11.1 libclntsh.so
```

You must use the **tnsnames.ora** file to specify database access as defined in Oracle documentation. Genesys DB Client will load the **.tns** file.

The following is an example of TNS name content:

```
CMES =
  (DESCRIPTION =
    (ADDRESS = (PROTOCOL = TCP)(HOST =<your oracle host>)(PORT = 1521))
    (CONNECT_DATA =
      (SERVER = DEDICATED)
      (SERVICE_NAME = cmes)
    )
  )
```

With this definition in the **.tns** file, the parameters of the Genesys Database Access Point can be set as follows:

```
dbengine=oracle
dbserver=<your oracle host>:1521/cmes
dbname=
username=<oracle schema user>
password=<oracle schema user's password>
```

Using Oracle Instant Client

Instead of a full Oracle client installation, you can use the Instant Client package from Oracle,

downloadable from [here](#).

For core Genesys servers to work, you must have the Basic package. If you have to perform conversion of character set encodings for languages other than English, make sure that the Instant Client package contains all necessary encoding tables. If you cannot find the proper package of Instant Client, you may want to use a full Oracle installation.

Connectivity to an Oracle database relies on TCP/IP to work between the Oracle server and client. You do not need to set up the **ORACLE_HOME** or **ORACLE_SID** environment variables. However, you must specify the full path to the folder where you put the Oracle Instant Client in the appropriate environment variable—**PATH** for Windows, **LIBPATH** for AIX, or **LD_LIBRARY_PATH** for Linux and Solaris.

For example, the configuration of Genesys Database Access Points without using TNS should be as follows:

```
dbengine=oracle
dbserver=<oracle host>:1521/<oracle service name>
dbname=
username=<oracle schema user>
password=<oracle schema user's password>
```

You can still use TNS-based connection information with Instant Client if you set up the **TNS_ADMIN** environment variable, or you can use the SQL Connect URL string <host>[:port]/<service name>. Both are described in Oracle Instant Client documentation.

Service Name

Instant Client requires a Service Name, rather than the SID required by the full Oracle installation package. The Service Name can be found in the **tnsnames.ora** file, which is found in the **<oracle home>/network/admin** folder on the server. For example, in the following excerpt from the **tnsnames.ora** file, the SID appears below ORCL, and the Service Name is **orcl.us.int.genesyslab.com**.

```
ORCL =
  (DESCRIPTION =
    (ADDRESS = (PROTOCOL = TCP)(HOST = <IP of a host>)(PORT = 1521))
    (CONNECT_DATA =
      (SERVER = DEDICATED)
      (SERVICE_NAME = orcl.us.int.genesyslab.com)
    )
  )
```

Using Oracle Database with National Languages

Single Language Deployment

You must create all Oracle databases using the same character set, such as WE8MSWIN1252. You must select an encoding that matches Microsoft Windows Operating System default encoding for a selected language, so that applications, like Interaction Routing Designer, display data correctly.

On every host that has a Genesys application accessing an Oracle database, make sure that the

NLS_LANG environment variable is set to match the language and character encoding of data in the Oracle database, as defined in the following table . For example, **NLS_LANG=AMERICAN_AMERICA.WE8MSWIN1252**.

[+] Show table

Operating System Locale	NLS_LANG Environment Variable Value
Arabic (U.A.E.)	ARABIC_UNITED ARAB EMIRATES.AR8MSWIN1256
Bulgarian	BULGARIAN_BULGARIA.CL8MSWIN1251
Catalan	CATALAN_CATALONIA.WE8MSWIN1252
Chinese (PRC)	SIMPLIFIED CHINESE_CHINA.ZHS16GBK
Chinese (Taiwan)	TRADITIONAL CHINESE_TAIWAN.ZHT16MSWIN950
Croatian	CROATIAN_CROATIA.EE8MSWIN1250
Czech	CZECH_CZECH REPUBLIC.EE8MSWIN1250
Danish	DANISH_DENMARK.WE8MSWIN1252
Dutch (Netherlands)	DUTCH_THE NETHERLANDS.WE8MSWIN1252
English (United Kingdom)	ENGLISH_UNITED KINGDOM.WE8MSWIN1252
English (United States)	AMERICAN_AMERICA.WE8MSWIN1252
Estonian	ESTONIAN_ESTONIA.BLT8MSWIN1257
Finnish	FINNISH_FINLAND.WE8MSWIN1252
French (Canada)	CANADIAN FRENCH_CANADA.WE8MSWIN1252
French (France)	FRENCH_FRANCE.WE8MSWIN1252
German (Germany)	GERMAN_GERMANY.WE8MSWIN1252
Greek	GREEK_GREECE.EL8MSWIN1253
Hebrew	HEBREW_ISRAEL.IW8MSWIN1255
Hungarian	HUNGARIAN_HUNGARY.EE8MSWIN1250
Icelandic	ICELANDIC_ICELAND.WE8MSWIN1252
Indonesian	INDONESIAN_INDONESIA.WE8MSWIN1252
Italian (Italy)	ITALIAN_ITALY.WE8MSWIN1252
Japanese	JAPANESE_JAPAN.JA16SJIS
Korean	KOREAN_KOREA.KO16MSWIN949
Latvian	LATVIAN_LATVIA.BLT8MSWIN1257
Lithuanian	LITHUANIAN_LITHUANIA.BLT8MSWIN1257
Norwegian	NORWEGIAN_NORWAY.WE8MSWIN1252
Polish	POLISH_POLAND.EE8MSWIN1250
Portuguese (Brazil)	BRAZILIAN PORTUGUESE_BRAZIL.WE8MSWIN1252
Portuguese (Portugal)	PORTUGUESE_PORTUGAL.WE8MSWIN1252
Romanian	ROMANIAN_ROMANIA.EE8MSWIN1250
Russian	RUSSIAN_CIS.CL8MSWIN1251
Slovak	SLOVAK_SLOVAKIA.EE8MSWIN1250

Operating System Locale	NLS_LANG Environment Variable Value
Spanish (Spain)	SPANISH_SPAIN.WE8MSWIN1252
Swedish	SWEDISH_SWEDEN.WE8MSWIN1252
Thai	THAI_THAILAND.TH8TISASCII
Spanish (Mexico)	MEXICAN_SPANISH_MEXICO.WE8MSWIN1252
Spanish (Venezuela)	LATIN_AMERICAN_SPANISH_VENEZUELA.WE8MSWIN1252
Turkish	TURKISH_TURKEY.TR8MSWIN1254
Ukrainian	UKRAINIAN_UKRAINE.CL8MSWIN1251
Vietnamese	VIETNAMESE_VIETNAM.VN8MSWIN1258

For more information, see the Oracle documentation [here](#).

If you are unable to setup MS Windows compatible character encoding when creating the Oracle database, make sure that the Oracle client software on all hosts with Genesys applications has been set to use character encoding that matches the target as close as possible, by following these steps:

1. Set up **NLS_LANG** to use the closest compatible encoding. For example, WE8ISO8858P1 to match WE8MSWIN1252 if you are using Linux to host Genesys applications that should access Oracle Databases.
2. Make sure that Oracle client software contains NLS tables allowing conversion between character encoding of the database and the host. Refer to Oracle documentation for more information about supported character conversions.

With your environment set up this way, you can use character data in a single language (such as French) for all information stored and transmitted between Genesys applications.

Multi-Language Deployment

To enable storage and processing of data in multiple languages using Oracle Databases, you must create all your database instances using the AL32UTF8 character set. For example:

```
CREATE DATABASE orclutf8
...
  CHARACTER SET AL32UTF8
  NATIONAL CHARACTER SET AL16UTF16
```

On every host that has a Genesys application accessing an Oracle database, make sure the **NLS_LANG** environment variable is set to match the character encoding of data in the Oracle database; for example, **NLS_LANG=**.UTF8.

Using Oracle TAF

Genesys supports using the Oracle Real Application Cluster to provide redundant access to database storage. You must use the TNS file to define cluster access, as specified in Oracle documentation.

For example:

```
LORAC =
  (DESCRIPTION =
    (ADDRESS = (PROTOCOL = TCP)(HOST =<oracle RAC listener> )(PORT = 1521))
    (CONNECT_DATA =
      (SERVER = DEDICATED)
      (SERVICE_NAME =<oracle service name>)
      (FAILOVER_MODE =
        (TYPE = SELECT)
        (METHOD=BASIC)
        (RETRIES = 2)
        (DELAY = 1)
      )
    )
  )
```

The **RETRIES** and **DELAY** parameters might affect how long the Genesys application will wait for Oracle to respond before it attempts to reconnect. Refer to the Oracle TAF guide for more details.

Failure of an Oracle 12g RAC Database

The Oracle 12g Real Application Cluster (RAC) DBMS includes a client-side feature called Transparent Application Failover (TAF). If an instance of a database fails, TAF automatically reconnects to a surviving database instance (node).

However, TAF only restores the connection; it is the responsibility of the application to restart on the new node any operations that were in process on the failed node. These operations could be any of the following:

- Individual Data Manipulation Language (DML) statements, such as INSERT, UPDATE, and DELETE.
- Active transaction involving DML statements, issuing ROLLBACK instructions to these transactions first.
- Active binding packages.

To support Oracle 12g RAC in TAF mode, Configuration Server can optionally resubmit DML statements (DML transactions or binding package execution) when the appropriate error messages are received from the DBMS. This is implemented using the configuration option **dml-retry**. Refer to the *Framework Configuration Options Reference Manual* for the full description of this option.