

# **GENESYS**

This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

# Deployment Guide

Configure a Cluster of Co-browse Servers

## Configure a Cluster of Co-browse Servers

Genesys Co-browse supports load balancing using Stickiness.

Load balancing is enabled by configuring a cluster of Co-browse Servers. Cassandra is embedded in Genesys Co-browse Server, so when you set up a cluster of Genesys Co-browse servers, each server may also act as a Cassandra node. You configure the Cassandra nodes by setting configuration options in the cassandraEmbedded section of the Co-browse Server application.

Complete the following steps to implement load balancing:

## 1. Set up 2 or more Co-browse Server nodes

#### Tip

To determine the how many nodes your Co-browse cluster needs, use the Genesys Co-browse Sizing Calculator.

#### 8.5.000

For Co-browse 8.5.000, you must set up a cluster of Co-browse Servers to enable load balancing. For each Co-browse Server in your planned cluster, complete the procedures on the Install Genesys Co-browse Server page.

If the Co-browse servers reside on the same machine, you must configure the applications to use different ports for Jetty and the embedded Cassandra. This will prevent port conflicts among your Co-browse Servers.

### **Important**

Every Co-browse Server in the cluster generally plays the same role as the others, except some embedded Cassandra nodes act as seed nodes. This means that to see consistent behavior on the cluster, regardless of which server serves requests, all Co-browse Servers should have the same options set in their application objects in Configuration Server. The rule of thumb is to configure the cluster servers the same, unless it is absolutely necessary to do otherwise (for example, a port is busy on a machine). This simplifies maintenance of production deployments.

#### 8.5.001 +

For Co-browse 8.5.001+, you must set up a cluster of Co-browse Nodes to enable load balancing. To do this, complete the procedures to create Application objects for a Co-browse Cluster and Co-browse Nodes. Follow the installation steps outlined in the **8.5.001+** tab in the Creating the Co-browse Server Application Object in Genesys Administrator section.

If the Co-browse Nodes reside on the same machine, you must configure the applications to use different ports for Jetty and the embedded Cassandra. This will prevent port conflicts among your Co-browse Nodes.

## 2. Configure the Cassandra cluster

#### Configure the Cassandra cluster

**Prerequisite:** You have completed Set up 2 or more Co-browse Servers.

#### External Cassandra Cluster Setup

#### **Important**

For supported versions of Cassandra, see Genesys Co-browse in the Supported Operating Environment Reference Guide.

External Cassandra cluster deployment is thoroughly described in the official Cassandra documentation. See the following:

- Planning a cluster deployment
- Initializing a cluster
- External Cassandra Access Configuration

#### Embedded Cassandra Cluster Setup

#### **Important**

Starting in 8.5.0, Embedded Cassandra mode is deprecated in Genesys Co-browse; support for this mode will be discontinued in 9.0.

An Embedded Cassandra cluster is setup similarly to an external Cassandra except that embedded Cassandra node settings are provided either through Configuration Server options or an external cassandra.yaml file.

#### Start of procedure

Complete the steps below for each Co-browse application you created in Set up 2 or more Co-browse Servers:

- 1. Open Genesys Administrator and navigate to PROVISIONING > Environment > Applications.
- 2. Select the Co-browse application and click Edit.
- 3. In the Options tab, locate the cassandraEmbedded section and update the following options:
  - 1. listenAddress Set this value to the IP of the node (listenAddress in cassandra.yml).
  - 2. rpcAddress Set this value to the IP of the node (rpcAddress in cassandra.ymal).
  - 3. seedNodes Set this value to the IP of the first node (seedNodes in cassandra.yaml).
  - 4. clusterName (optional) This name should be the same for each node (name in cassandra.yaml).
- 4. Click Save & Close.

#### **End of procedure**

#### Replication Strategy

By default, Co-browse server activates NetworkTopologyStrategy as a replication strategy. NetworkTopologyStrategy is recommended for production Cassandra deployments and is supported by GossipingPropertyFileSnitch. GossipingPropertyFileSnitch relies on the cassandra-rackdc.properties file. Make sure the data center data center names defined in this file (one for each Cassandra node) correspond to data center names defined in the replicationStrategyParams option.

The cassandra-rackdc.properties file location depends on the type of Cassandra cluster:

- External Cassandra—see the conf subdirectory of the Cassandra installation directory. For more
  information, see <a href="http://docs.datastax.com/en/cassandra/2.0/cassandra/architecture/">http://docs.datastax.com/en/cassandra/2.0/cassandra/architecture/</a>
  architectureSnitchGossipPF c.html.
- Embedded Cassandra—see the resources subdirectory of the server directory. For example, <Co-browse Server Install Directory>/server/resources.

#### Replication Factor

Replication factor configures the number of copies of data to keep in the cluster. Typically, three copies is enough for most scenarios (provided you have at least three nodes in your cluster). The replication factor can be increased to achieve higher redundancy levels. Set the replication factor in the replicationStrategyParams option to a number less than or equal to the number of nodes.

## 3. Verify the status of the Cassandra cluster

**Prerequisite:** You have a separate installation of Cassandra 2.x (2.1.3+, the same version used in Co-browse).

- 1. Start the first node and wait until it starts listening.
- 2. Start all other nodes in your cluster.
- 3. Open a command line and run <cassandra home>\bin\cassandra-cli.bat -h <ip of first node> -p <cassandra rpcPort>, where <ip of first node> is the IP of the first node in your cluster and <cassandra rpcPort> is the value you configured for rpcPort.
- 4. Enter the following command: describe cluster. The output should look similar to the following:

```
[default@unknown] describe cluster;
Cluster Information:
    Snitch: org.apache.cassandra.locator.SimpleSnitch
    Partitioner: org.apache.cassandra.dht.RandomPartitioner
    Schema versions:
    6c960880-1719-11e3-0000-242d50cf1fbf: [192.168.00.1, 192.168.00.2, 192.168.00.3]
```

The list of IP address in square brackets ([192.168.00.1, 192.168.00.2 ...]) should match all the nodes in your cluster.

#### **End of procedure**

## 4. Configure the load balancer

See Configuring a Load Balancer for Co-browse Cluster for details about configuring the load balancer and sample configurations for Nginx and Apache.

#### Tip

In Co-browse 8.5.002+, the agent side uses the cluster URL while the end user (master) side uses the URL in the Website Instrumentation. You can have two load balancers, an internal load balancer for agents which you specify in the cluster URL option and a public load balancer for end users to use in the JS instrumentation. Depending on your infrastructure's setup, two load balancers may benefit traffic.

## 5. Modify the website instrumentation

You must modify the URLs in your Co-browse instrumentation scripts to point to your configured load

balancer. See Website Instrumentation for details about modifying the script.

#### **Important**

Starting with Co-browse 8.5.002+, the consumer (master) side always uses the URL in the JS instrumentation for css-proxy and url-proxy.

If you are using the Co-Browse proxy to instrument your site, you will need to modify the URLs in the in proxy's map.xml file. See Test with the Co-browse Proxy for details about modifying the xml file.

#### Warning

The Co-browse proxy should only be used in a lab environment, not in production.

## 6. Modify the agent side and controller configuration

Configure the Co-browse Server applications

- 8.5.000—Modify the url option in the cluster section of all your Co-browse Server applications.
- 8.5.001—Modify the url option in the cluster section of your Co-browse Cluster application.

See the cluster section for details.

#### Tip

In Co-browse 8.5.002+, the agent side uses the cluster URL while the end user (master) side uses the URL in the Website Instrumentation. You can have two load balancers, an internal load balancer for agents which you specify in the cluster URL option and a public load balancer for end users to use in the JS instrumentation. Depending on your infrastructure's setup, two load balancers may benefit traffic.

You must also set up a similar configuration for the Genesys Co-browse Plug-in for Workspace

Desktop Edition. To support this, you might consider setting up two load balancers:

- public This load balancer should have a limited set of Co-browse resources. For example, it should not include session history resources.
- private This load balancer should have all Co-browse resources and it should be placed in the network so that it is accessible only from the corporate intranet. It should only be used for internal applications, such as Workspace Desktop Edition.

Complete the procedure below to configure the plug-in to support the Co-browse cluster:

#### Configure the Co-browse Plug-in for Workspace Desktop Edition

See Configuring Workspace Desktop Edition to allow the Plug-in to work with co-browsing.

## 7. Configure Genesys Workspace Web Edition

If you use Workspace Web Edition on the agent side, you must configure it to work with Co-browse. For instructions, see Configure Genesys Workspace Web Edition to Work with Co-browse.

#### 8. Launch and test

To test your set-up, create a Co-browse session, join it as an agent and do some co-browsing. If you can do this, your configuration was successful.

#### **End of procedure**