



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

# Genesys Info Mart Physical Data Model for an Oracle Database

Table BGS\_SESSION\_DIM

# Table BGS\_SESSION\_DIM

## Description

**Introduced:** 8.5.011

In partitioned databases, this table is not partitioned.

This dimension table allows Bot Gateway Server (BGS) session facts to be described based on characteristics of the session, such as how the session ended.

### Tip

To assist you in preparing supplementary documentation, click the following link to download a comma-separated text file containing information such as the data types and descriptions for all columns in this table: [Download a CSV file](#).

**Hint:** For easiest viewing, open the downloaded CSV file in Excel and adjust settings for column widths, text wrapping, and so on as desired. Depending on your browser and other system settings, you might need to save the file to your desktop first.

## Column List

### Legend

Column	Data Type	P	M	F	DV
ID	NUMBER(10)	X	X		
REJECTED_TO_START	NUMBER(10)		X		0
ENDED_ABNORMALLY	NUMBER(10)		X		0
ENDED_BY	VARCHAR2(50 CHAR)		X		NO_VALUE
END_REASON	VARCHAR2(50 CHAR)		X		NO_VALUE

Table BGS\_SESSION\_DIM

Column	Data Type	P	M	F	DV
END_RESULT	VARCHAR2(50 CHAR)		X		NO_VALUE
CREATE_AUDIT_KEY	NUMBER(19)		X	X	

## ID

The primary key of this table. This ID is referenced from other tables as BGS\_SESSION\_DIM\_KEY.

## REJECTED\_TO\_START

Indicates whether the session was rejected before it started: 0 = No, 1 = Yes.

If the session was rejected (REJECTED\_TO\_START=1), the columns for other session statistics in this table are populated with the default values defined in the schema.

## ENDED\_ABNORMALLY

Indicates whether the session ended abnormally for a technical reason (for example, a protocol or connection error resulted in disconnection of the bot from the session): 0 = No, 1 = Yes.

## ENDED\_BY

The type of participant that initiated termination of the BGS session. Possible values are:

- AGENT
- CLIENT
- SYSTEM
- BOT
- CBP

For more information about the meaning of the values, see [Integrating BGS with Genesys Historical Reporting](#) in the *Bot Gateway Server Quick Start Guide*.

## END\_REASON

The reason the BGS session was terminated. For information about possible values, see [Integrating BGS with Genesys Historical Reporting](#) in the *Bot Gateway Server Quick Start Guide*.

## END\_RESULT

The business result of the session: Success or Fail. In the initial BGS implementation of support for reporting, BGS does not populate the applicable data attribute, and END\_RESULT will always be populated with the default value defined in the schema.

## CREATE\_AUDIT\_KEY

The surrogate key that is used to join to the CTL\_AUDIT\_LOG control table. The key specifies the lineage for data creation. This value can be useful for aggregation, enterprise application integration (EAI), and ETL tools—that is, applications that need to identify newly added data.

## Index List

CODE	U	C	Description
I_BGS_SESSION_DIM	X		Ensures that the combinations of values that are stored in the dimension table are unique.

## Index I\_BGS\_SESSION\_DIM

Field	Sort	Comment
REJECTED_TO_START	Ascending	
ENDED_ABNORMALLY	Ascending	
ENDED_BY	Ascending	
END_REASON	Ascending	
END_RESULT	Ascending	

## Subject Areas

No subject area information available.