

## **GENESYS**

This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

## Genesys Mobile Services Deployment Guide

Using Callbacks without DFM

## Using Callbacks without DFM

To use the Callback strategy without using DFM, the GMS API can be used with the Session/Fetch requests (HTTP requests) using the URL configured in the **external\_url\_base** configuration option in the **server** section.

The GMS API will be called from the Callback strategy using the Session/Fetch requests (HTTP request), the URL used for these HTTP operations is the GMS application option **external\_url\_base** in **server** section. The following options are available to configure this feature.

- \_enable\_gms\_dfm
- · fetch timeout
- · \_fetch\_retry\_attempt
- · fetch retry delay
- · services credentials

```
[service.<callback service name>]
...
_enable_gms_dfm=false
...
```

You can also create a GMS Services Credentials Transaction List when accessing the GMS API with credentials:

When GMS API are using credentials, create GMS Services Credentials Transaction List (called for example GMS Credentials) with the following annex:

```
[server]
username=username
password<password>
```

The server username is the same username as the **username** option in GMS Application options in **server** section and the server password is the same password as the **password** option in GMS Application options in **server** section.

Add an services credentials option in Callback service section:

```
[service.<callback service name>]
...
_enable_gms_dfm=false
...
_services_credentials=GMS_Credentials
```

## Limitations

When using the Callback strategy without using DFM, the following limitations apply:

- The Session/Fetch HTTP request uses the URL from GMS: external\_url\_base option value.
- There are no round-robin hosts as in the DFM definition.
- Credentials on GMS API are activated on server section only (not per service) via a Transaction List.