



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Genesys PureConnect Data Extractor Application

Installation and Setup


4/23/2025

Installation and Setup


Make sure you have everything mentioned in the [prerequisites](#).

Follow the procedure below to install and set up the PureConnect Data Extractor application in the PureConnect server.

1. Log in to the PureConnect server as a **Windows** administrator.
2. From the **Performance DNA** release folder, copy the **Apps.PureConnectData** folder to a known location on the PureConnect server, for example, **C:\apps.PureConnectData**.



3. Create a working folder to store extracted data files, for example, **C:\DataExtractor**.
4. Run the PureConnect Interaction Administrator application from the Windows **Start** menu and log in as a PureConnect administrator.
5. Click and expand **System Configuration** from the left pane and then select the **Data Extractor** menu.



6. On the right pane, right-click the **Configuration** item and then select **Properties**.
7. In the **Data Extractor Configuration** dialog that appears, modify the following values and leave other fields with default values:
 - **Select a data source** - set this drop-down list value to **IC Report Logs**.
 - **Select output path** - browse and locate the working folder created in step 3.
8. Click **Ok**.