

GENESYS

This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

GVP Documentation Supplement

Changed GVP Configuration Options

Changed GVP Configuration Options

Return to Supplement Table of Contents

The configuration options routefailovertime and routerecoverytime are now unhidden in the MCP configuration template.

Option: transport.routefailovertime **Application:** Media Control Platform

Section: sip Valid values: 1-32 Takes effect: At restart

Specifies the failover time, in seconds, for SIP static routing and DNS HA routing. If a SIP request has not received a response within the failover time, and SIP static routing or DNS HA routing is enabled, then the SIP request will be retransmitted to an alternate route.

Option: transport.routerecoverytime **Application:** Media Control Platform

Section: sip Valid Values: 1-600 Takes effect: At restart.

Specifies the recovery time, in seconds, for SIP static routing and DNS HA routing. When SIP static routing or DNS HA routing is enabled and the route is marked as unavailable due to an error or a SIP response timeout, then the route will be marked as available again after the recovery time.

These two options were added to Resource Manager for release 8.5.0:

Option: pass-tenantid-parameter-to-gateway

Application: Resource Manager

Section: rm

Valid Values: true (default) or false

- Set to false to specify that RM does not pass the tenant-id RURI parameter (specified by gvp-tenant-id) in the request to the Gateway or an external SIP service.
- Set to true to specify that RM passes the tenant-id RURI parameter in the request to the Gateway or an
 external SIP service.

Option: ignore-ruri-tenant-dbid **Application:** Resource Manager

Section: rm

Valid Values: true (default) or false

- Set to true to specify that RM does not use the tenant-dbid parameter received through the incoming INVITE RURI.
- Set to false to specify that RM uses the tenant-dbid parameter.

Changed GVP Configuration Options					