



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Workspace Desktop Edition Deployment Guide

Business Continuity Options

4/8/2025

Business Continuity Options

Contents

- [1 Business Continuity Options](#)
 - [1.1 Business Continuity](#)

Business Continuity

Options that have the `disaster-recovery.*` prefix are used to configure the Business Continuity functionality.

`disaster-recovery.auto-restore`

- Default Value: `true`
- Valid Values: `true`, `false`
- Changes take effect: When the application is started or restarted.
- Description: Specifies whether agent should be relogged in to the Preferred site as soon as it is available.

`disaster-recovery.disable-login-errors`

- Default Value: `false`
- Valid Values: `true`, `false`
- Changes take effect: When the application is started or restarted.
- Description: Specifies whether Interaction Workspace should display media voice login errors in the Login window.

`disaster-recovery.enabled`

- Default Value: `false`
- Valid Values: `true`, `false`
- Changes take effect: When the application is started or restarted.
- Description: Specifies whether Business Continuity is enabled.

`disaster-recovery.preferred-site`

- Default Value: Preferred
- Valid Values: A unique symbolic name of the site or location to be used as the preferred login site. Letters A to Z and a to z. Numbers 0 through 9. The underscore, @ and space characters.
- Changes take effect: When the application is started or restarted.
- Description: Specifies the site name to be used as preferred when connecting to any back-end server. That is, it specifies the name of the preferred connection site for the application, tenant, agent Group, or agent. There must be a connection to this site in the Connections tab of the corresponding server. This option should match the name specified by the `disaster-recovery.site` option that is configured on the server object.

disaster-recovery.peer-site

- Default Value: DRPeer
- Valid Values: A unique symbolic name of the site or location to be used as the preferred login site. Symbolic name of the site or location. Letters A to Z and a to z. Numbers 0 through 9. The underscore, @ and space characters. Letters A to Z and a to z. Numbers 0 through 9. The underscore, @ and space characters.
- Changes take effect: When the application is started or restarted.
- Description: Specifies the name of the site that is to be the secondary (Business Continuity peer) when connecting to any back-end server for the site that is specified by the `disaster-recovery.site` option. There must be a connection to this site in the Connections tab of the corresponding server.

disaster-recovery.restore-agent-state

- Default Value: true
- Valid Values: true, false
- Changes take effect: When the application is started or restarted.
- Description: Specifies whether Interaction Workspace should restore last agent state after logging on to the reserved site after the current site fails.

disaster-recovery.timeout

- Default Value: 60
- Valid Values: A valid positive integer.
- Changes take effect: When the application is started or restarted.
- Description: Specifies time in seconds to wait after Preferred Site HA Pair disconnection is detected before switching connection to the Business Continuity site.

disaster-recovery.wait-for-sipphone-timeout

- Default Value: 0
- Valid Values: A valid positive integer.
- Changes take effect: When the application is started or restarted.
- Description: Specifies time in seconds during which an agent should wait for SipEndpoint before a disaster is considered. A value of 0 means no limit.