



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Genesys Designer Help

Custom Service Block

Custom Service Block

Contents

- [1 Custom Service Block](#)
 - [1.1 Service Details tab](#)
 - [1.2 Results tab](#)

You can use the **Custom Service** block to access a custom service that was created by Genesys for your company.

You can provide input to the service. The resulting variable from the block is true if the service request is successful, otherwise the result is false. This result is available for use in later blocks.

Service Details tab

Select the service name and action to use in this **Custom Service** block.

Select **Disable DTMF buffering** if you want to prevent any DTMF inputs made during fetch audio playback from being buffered and carried forward into subsequent **User Input** or **Menu** blocks.

If you enable the **Play fetch audio** check box, you can specify an audio resource to play to the caller while the custom service is being fetched.

Important

Only Announcements containing audio files are supported. TTS audio will not be played.

- Enable the check box beside the **Play fetch audio** check box to specify a variable.
- In the **Play fetch audio minimum for** field, you can enter the minimum length of time to play the audio, even if the custom service has arrived in the meantime.
- In the **Start fetch audio after** field, you can enter a period of time to wait before audio is played.

Important

In the **Self Service** phase, fetch audio playback stops when the end of the audio file is reached, even if the service request is still in progress. In the **Assisted Service** phase, fetch audio playback loops until the service request times out.

Input Parameters

In the **Input Parameters** tab, specify the input expected by the custom service.

- **Name** - Specify the name of the parameter expected by the custom service.
- **Type** - The type of parameter (variable or literal).
- **Value** - Specify the parameter value to pass to the input.

Output Parameters

In the **Output Parameters** tab, specify how and where to store the results of the custom service.

- **Variable Name** - Select the application variable in which to store the data.
- **JSON Expression** - Specify the key in which you expect the result to be in the response object. See the code sample and table below for an example.

```
{
  "thing": {
    "otherthing": "abc"
  },
  "arrayofthings": [
    "thing1", "thing2"
  ]
}
```

JSON Expression	Result
thing.otherthing	abc
arrayofthings[1]	thing2

Properties - Custom Service



This block executes custom services provided by Designer

Service details Results

Service Name:

Service Request Timeout: Seconds

Disable DTMF buffering

Play fetch audio:

Parameters

Input Parameters Output Parameters

Key Value pairs

Results tab

Select a variable to store the outcome status (**true** or **false**) of the Custom Service request.

Custom Service Block

You must also select an action to take if the fetch operation is not successful. You can choose to "Continue with normal processing" or "Execute error handler blocks".

If you select "Execute error handler blocks", an **Error Handler** child block appears under the **Custom Service** block.

Use the **Error Handler** block to send the application to another target block that you select from the **Navigation** tab, or add child blocks that will perform the actual error handling.

Examples

In this example, the **Navigation** tab is used to specify a target block. If there is an error, the application will go to the **Play Message** block and play an error message:

The screenshot shows the Genesys Designer interface. On the left, the 'Application Flow' pane displays a sequence of blocks: Initialize, Self Service, Assisted Service, User Input, Segmentation, Segmentation - decide how to route call, Route Call - route to default number for all cases, Setup Survey, Custom Service, Error Handler, Terminate Call, Play Message - Sorry, an error occurred, and Finalize. The 'Error Handler' block is highlighted. On the right, the 'Properties - Error Handler' pane is open, showing the 'Navigation' tab. Under 'Navigation', the 'By Name' radio button is selected. A search box contains 'Play Message - Sorry, an error occurred', and a dropdown menu shows this block as the selected target. A handwritten arrow points from the 'Error Handler' block in the flow to the 'Play Message' block in the properties pane, with the text 'Error? Go to the specified block' written next to it.

In this example, a child block is used to invoke a module that will perform the error handling:

The screenshot shows the Genesys Designer interface. On the left, the 'Application Flow' pane displays a sequence of blocks: Initialize, Self Service, Assisted Service, User Input, Segmentation, Segmentation - decide how to route call, Route Call - route to default number for all cases, Setup Survey, Custom Service, Error Handler, My Error Handling Logic, Terminate Call, and Finalize. The 'Error Handler' block is highlighted, and it contains a child block named 'My Error Handling Logic'. On the right, the 'Properties - My Error Handling Logic' pane is open, showing the 'Module' tab. Under 'Module', the 'Shared Modules' radio button is selected. A search box contains 'some_error_handling_logic', and a dropdown menu shows this module as the selected target. Below the search box is a table with the following data:

	Version	Label	Note	Created
●		Latest	Use latest unpublished save.	09/28/2016

Tip

- If you select a target block from the **Navigation** tab, then any child blocks you've added to the **Error Handler** parent block are ignored.
- Standard validation rules still apply — any child blocks that you add to the **Error Handler** block must be valid for the application phase in which they are being used.