



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

# Framework Deployment Guide

Framework Database Replication for Disaster Recovery Using Oracle GoldenGate

5/12/2025

---

## Contents

- 1 Framework Database Replication for Disaster Recovery Using Oracle GoldenGate
  - 1.1 Operation
  - 1.2 Configuration Example
  - 1.3 File and Script Examples

# Framework Database Replication for Disaster Recovery Using Oracle GoldenGate

This section describes the configuration of a Disaster Recovery / Business Continuity architecture, as described in [Disaster Recovery Architecture](#). The configuration is based on the Oracle GoldenGate software.

## Important

This page is not a step-by-step guide. It is a description of reference architecture; it tells you what components are needed and where. A customer can copy a file (on Linux), create an image of their entire Virtual Machine and clone it (this is the recommended way, keeping in mind the complexity of the Disaster Recovery architecture and the number of components involved), or deploy each additional installation package individually and adjust the resulting configuration (since each installation package can alter aspects of configuration objects, such as changing startup paths).

## Operation

### System Startup Procedure and Normal Operating Mode

1. Start the replication process.

#### Tip

For reference, use the Oracle® GoldenGate Windows and UNIX Administrator's Guide 11g Release 1 (11.1.1) E17341-01 (Ref 1.)

- a. On the MAIN and SECONDARY systems, run the script that removes INSERT, UPDATE, and DELETE permissions to CFG\_DB and MS\_DB users.
- b. Use the START MANAGER command to start manager processes at both sites.
- c. At the SECONDARY site, using GGSCI, start REPLICATs in preparation to receive changes from the Configuration and Log Databases on the live MAIN system.

```
START REPLICAT CSP
START REPLICAT MSP
```

- d. At the MAIN site, using GGSCI, start REPLICAT MSS in preparation to receive changes from the log Database on the live SECONDARY system.

```
START REPLICAT MSS
```

- e. On the MAIN site system, alter the primary Extract to begin capturing data based on the current timestamp. Otherwise, Extract will spend unnecessary time looking for operations that date back to the time that the group was created using the ADD EXTRACT command.

```
ALTER EXTRACT CSP, BEGIN NOW  
ALTER EXTRACT MSP, BEGIN NOW
```

- f. On the SECONDARY site system, alter the secondary Extract to begin capturing data based on the current timestamp. Otherwise, Extract will spend unnecessary time looking for operations that date back to the time that the group was created with the ADD EXTRACT command.

```
ALTER EXTRACT MSS, BEGIN NOW
```

- g. On the MAIN system, start the primary Extracts so they are ready to capture transactional changes.

```
START EXTRACT CSP  
START EXTRACT MSP
```

- h. On the SECONDARY system, start the secondary Extract so it is ready to capture transactional changes at the secondary Log Database.

```
START EXTRACT MSS
```

- i. On the MAIN system, do the following:
  - Run the script that grants INSERT, UPDATE, and DELETE permissions to CFG\_DB and MS\_DB users.
  - Run the script that enables triggers and cascade delete constraints.
- j. On the SECONDARY system, do the following:
  - Run the script that grants INSERT, UPDATE, and DELETE permissions to MS\_DB users.
  - Run the script that enables triggers and cascade delete constraints.

At this point, the database system is ready for normal operation.

## 2. Start the system.

- a. Run the scripts that switchover cfgmaster host name IP resolution to a MAIN live system.
- b. Launch the MAIN live Master Configuration Server primary/backup pair at Site 1.
- c. Launch the MAIN live Master Solution Control Server to control the main Master Configuration Server pair at Site 1.
- d. Launch the MAIN Message server at Site 1 to support communications for Solution Control Servers controlling site components.
- e. Launch Solution Control Server at Sites 1 and 2.
- f. Using Solution Control Server, start the Configuration Server Proxy pair at Sites 1 and 2.
- g. Using Solution Control Server, start the Framework site components.

## Disaster Recovery Switchover

At this point, all system components residing at the MAIN site on Host 3 are lost and not running:

- MAIN live Master Configuration Server primary/backup pair
- MAIN live Master Solution Control Server
- MAIN Message server at Site 1
- Oracle database
- Oracle GoldenGate

Operations on other sites can be continued non-stop in limited mode without a configuration change using Configuration Server Proxies running in Read-Only mode until the SECONDARY Master Configuration Server is brought on-line.

Perform the following steps to move activity to the SECONDARY live Master Configuration Server primary/backup pair.

1. On the SECONDARY live standby system, using GGSCI, issue the LAG REPLICAT command until it returns At EOF (end of file) to confirm that REPLICAT applied all of the data from the trail to the database.

```
LAG REPLICAT CSP
LAG REPLICAT MSP
```

2. Stop the REPLICAT processes.

```
STOP REPLICAT CSP
STOP REPLICAT MSP
```

3. On the SECONDARY system, run the script that grants INSERT, UPDATE, and DELETE permissions to the CFG\_DB and MS\_DB users.

4. Run the script that enables triggers and cascade delete constraints.

5. Launch the SECONDARY live Master Configuration Server primary/backup pair at Site 2.

6. Launch the SECONDARY live Master Solution Control Server to control the MAIN Master Configuration server pair at Site 2.

7. Launch the SECONDARY Message Server at Site 2 to support communication for Solution Control Servers controlling site components.

8. Run the dnscmd **script** that switches over cfgmaster host name IP resolution to a MAIN live system.

9. On the host running Configuration Server Proxies, run the **switch over script** to flush the DNS cache.

Communication Server Proxies reconnect to the SECONDARY live Master Configuration Server primary/backup pair and resume normal operation.

### Warning

Do not start the data EXTRACTOR on the SECONDARY system. The user transactions must accumulate in the SECONDARY system database until the MAIN system is to be

restored. Use the Secondary CSS replication group for database replication from SECONDARY to MAIN system before switching back to the MAIN system.

## Configuration Example

### Configuration for Oracle GoldenGate Replication Processes

1. At the MAIN and SECONDARY Oracle databases, create a user CFG\_DB for the Configuration Server database, and user MS\_DB for the Log Message Server database.
2. Using the initialization scripts in the Installation Package, create the database objects for the Configuration and Log Message Server Databases.
3. Use Oracle® GoldenGate Oracle Installation and Setup Guide11g Release 1 (11.1.1) E17799-01 (Ref 1.) and the examples of Parameter files below to configure the EXTRACT and REPLICAT processes.

Process	Table (EXTRACT) / Map (REPLICAT) Parameters
EXTRACT CSP	SEQUENCE CFG_DB.*;
EXTRACT CSS	TABLE CFG_DB.*; TABLEEXCLUDE CFG_DB.cfg_refresh;
EXTRACT MSP	SEQUENCE MS_DB_1.*;  TABLE MS_DB_1.*; TABLEEXCLUDE MS_DB_1.G_LOG_SCHEMA_INFO;
EXTRACT MSS	SEQUENCE MS_DB_2.*;  TABLE MS_DB_2.*; TABLEEXCLUDE MS_DB_2.G_LOG_SCHEMA_INFO;
REPLICAT CSS	MAP CFG_DB.*,TARGET CFG_DB.*;
REPLICAT CSP	MAPEXCLUDE CFG_DB.cfg_refresh;
REPLICAT MSP	MAP MS_DB_1.*,TARGET MS_DB_1.*;  MAPEXCLUDE MS_DB_1.G_LOG_SCHEMA_INFO;
REPLICAT MSS	MAP MS_DB_2.*,TARGET MS_DB_2.*;  MAPEXCLUDE MS_DB_2.G_LOG_SCHEMA_INFO;

4. Register Oracle GoldenGate EXTRACT and REPLICAT using GGSCI.

On the MAIN live system:

```
dblogin userid gg_user, password gg_password
register extract CSP, LOGRETENTION
register extract MSP, LOGRETENTION
```

On the SECONDARY live standby system:

```
dblogin userid gg_user, password gg_password
register extract CSS, LOGRETENTION
register extract MSS, LOGRETENTION
```

## Extract Group CSP at Primary Site Configuration Example

1. At MAIN system, start GGSCI.

2. Use the ADD EXTRACT command to create an Extract group CSP.

```
ADD EXTRACT CSP , TRANLOG, BEGIN NOW
Use TRANLOG as the data source option.
```

3. Use the ADD RMTTRAIL command to specify a remote trail to be created on the target system.

```
ADD RMTTRAIL ./CS, EXTRACT CSP
Use the EXTRACT argument to link this trail to the Extract group.
```

4. Use the EDIT PARAMS command to create a parameter file for the Extract group. Include the following parameters plus any others that apply to your database environment.

```
EDIT PARAMS CSP
```

CSP EXTRACT Parameters File Example:

```
EXTRACT CSP
RMTHOST <Secondary host name>, MGRPORT 7809
RMTTRAIL ./dirdat/CP
USERID gg_user PASSWORD gg_password
TRACE ./trace/cfg_db.trc
--Only use if DDL is configured
WILDCARDRESOLVE DYNAMIC
DDL INCLUDE MAPPED OBJNAME cfg_db.*
DDLOPTIONS ADDTRANDATA RETRYOP RETRYDELAY 20 MAXRETRIES 60 REPORT
-- TRANLOGOPTIONS DBLOGREADER, DBLOGREADERBUFSIZE 1024000
-- TRANLOGOPTIONS DBLOGREADERBUFSIZE 1024000

STATOPTIONS RESETREPORTSTATS
REPORT AT 00:01
REPORTROLLOVER AT 00:01
REPORTCOUNT EVERY 60 SECONDS, RATE
--
SEQUENCE cfg_db.*;
TABLE cfg_db.*;
TABLEEXCLUDE cfg_db.cfg_refresh;
```

## REPLICAT Group CSP at Secondary Site Configuration Example

1. At the SECONDARY system, start GGSCI.

2. Use the ADD REPLICAT command to create a Replicat group CSP.

```
ADD REPLICAT CSP, EXTTRAIL CSP, BEGIN NOW
Use the EXTTRAIL argument to link the Replicat group to the remote trail.
```

3. Use the EDIT PARAMS command to create a parameter file for the Replicat group. Include the following parameters plus any others that apply to your database environment:

```
EDIT PARAMS CSP
```

CSP REPLICAT Parameters File Example:

```
MACRO #exception_handler
BEGIN
, TARGET ggate.exceptions
, COLMAP ( rep_name = "rep"
, table_name = @GETENV ("GGHEADER", "TABLENAME")
, errno = @GETENV ("LASTERR", "DBERRNUM")
, dberrmsg = @GETENV ("LASTERR", "DBERRMSG")
, optype = @GETENV ("LASTERR", "OPTYPE")
, errtype = @GETENV ("LASTERR", "ERRTYPE")
, logrba = @GETENV ("GGHEADER", "LOGRBA")
, logposition = @GETENV ("GGHEADER", "LOGPOSITION")
, committimestamp = @GETENV ("GGHEADER", "COMMITTIMESTAMP"))
, INSERTALLRECORDS
, EXCEPTIONSONLY;
END;
-- This ends the macro
REPLICAT CSP
HANDLECOLLISIONS
--END RUNTIME
USERID gg_user, PASSWORD gg_password
ASSUMETARGETDEFS
DISCARDFILE ./dirrpt/CP.dsc, purge
TRACE ./trace/CSP.trc
-- INCLUDE ALL -- &
-- STATOPTIONS RESETREPORTSTATS
DDL INCLUDE ALL
--INCLUDE MAPPED -- &

-- DBOPTIONS SUPPRESSTRIGGERS, DEFERREFCONST
DBOPTIONS DEFERREFCONST
REPORT AT 00:01
REPORTROLLOVER AT 00:01
REPORTCOUNT EVERY 60 SECONDS, RATE
---
DDLOPTIONS REPORT
DDLERROR DEFAULT IGNORE
REPERROR (DEFAULT, EXCEPTION)
REPERROR (DEFAULT2, ABEND)
REPERROR (-1, EXCEPTION)
MAP CFG_DB.*,TARGET CFG_DB.*;
MAPEXCLUDE CFG_DB.cfg_refresh;
--MAP CFG_DB.* #exception_handler();
```

## Configuration of Genesys Components

### Important

LCA must be installed on every host on which Genesys components are running.

1. Start the replication process (P.3.3.1.1).
  2. Run the dnscmd **script** that switches over cfgmaster host name IP resolution to a MAIN live system.
  3. Install the MAIN live Master Configuration Server primary/backup pair at Site 1.
  4. Launch the MAIN live Master Configuration Server primary/backup pair at Site 1.
  5. Using Genesys Administrator connected to the Primary Master Configuration Server at Site 1, configure Master Solution Control Server, Message Server for distributed SCS, and Backup Master Configuration Server.
  6. Install Master Solution Control Server, Message Server for distributed SCS, and Master Backup Configuration Server on Site 1.
  7. Copy all backup and primary instances of Master Solution Control Server, Message Server for distributed SCS, and Master Configuration Server working directories to Site 2.
- Warning**

Never launch any instance of Master Configuration Server at Site 2 if it can access the Configuration Database that is also used by a running Configuration Server at Site 1.
8. Launch Master Solution Control Server and Message Server for distributed SCS.
  9. Using Genesys Administrator connected to the Primary Master Configuration Server at Site 1, configure and install Configuration Server Proxies, Solution Control Servers, and Message Servers for network logging for Sites 1 and 2.
  10. Start Configuration Server Proxies at Sites 1 and 2.
  11. Start Solution Control Servers at Sites 1 and 2.
  12. Start Message Servers for network logging at Sites 1 and 2.
  13. Install Framework Components at Site 1 using the Configuration Server Proxy host and port at Site 1.
  14. Install Framework Components at Site 2 using the Configuration Server Proxy host and port at Site 2.

## File and Script Examples

### EXTRACT Parameters File

```
EXTRACT <extract_name>
RMTHOST <target database host name>, MGRPORT 7809
RMTTRAIL ./dirdat/<rmtrail_name>
USERID <golden_gate_user> PASSWORD <golden_gate_password>
TRACE ./trace/<oracle_user_name>.trc
--Only use if DDL is configured
WILDCARDRESOLVE DYNAMIC
```

```
DDL INCLUDE MAPPED OBJNAME <oracle_user_name>.*
DDLOPTIONS ADDTRANDATA RETRYOP RETRYDELAY 20 MAXRETRIES 60 REPORT
-- TRANLOGOPTIONS DBLOGREADER, DBLOGREADERBUFSIZE 1024000
-- TRANLOGOPTIONS DBLOGREADERBUFSIZE 1024000

STATOPTIONS RESETREPORTSTATS
REPORT AT 00:01
REPORTROLLOVER AT 00:01
REPORTCOUNT EVERY 60 SECONDS, RATE
--
SEQUENCE <oracle_user_name>.*;
TABLE <oracle_user_name>.*;
TABLEEXCLUDE <exclude_filter>;
```

## REPLICAT Parameters File

```
MACRO #exception_handler
BEGIN
, TARGET ggate.exceptions
, COLMAP ( rep_name = "rep"
, table_name = @GETENV ("GGHEADER", "TABLENAME")
, errno = @GETENV ("LASTERR", "DBERRNUM")
, dberrmsg = @GETENV ("LASTERR", "DBERRMSG")
, optype = @GETENV ("LASTERR", "OPTYPE")
, errtype = @GETENV ("LASTERR", "ERRTYPE")
, logrba = @GETENV ("GGHEADER", "LOGRBA")
, logposition = @GETENV ("GGHEADER", "LOGPOSITION")
, committimestamp = @GETENV ("GGHEADER", "COMMITTIMESTAMP"))
, INSERTALLRECORDS
, EXCEPTIONSONLY;
END;
-- This ends the macro
REPLICAT <replicat_name>
HANDLECOLLISIONS
--END RUNTIME
USERID <golden_gate_user>, PASSWORD <golden_gate_password>
ASSUMETARGETDEFS
DISCARDFILE ./dirrpt/<discard_file_name>.dsc, purge
TRACE ./trace/<trace_file_name>.trc
-- INCLUDE ALL -- &
-- STATOPTIONS RESETREPORTSTATS
DDL INCLUDE ALL
--INCLUDE MAPPED -- &

-- DBOPTIONS SUPPRESSTRIGGERS, DEFERREFCONST
DBOPTIONS DEFERREFCONST
REPORT AT 00:01
REPORTROLLOVER AT 00:01
REPORTCOUNT EVERY 60 SECONDS, RATE
---
DDLOPTIONS REPORT
DDLERROR DEFAULT IGNORE
REPERROR (DEFAULT, EXCEPTION)
REPERROR (DEFAULT2, ABEND)
REPERROR (-1, EXCEPTION)
MAP <oracle_user_name>.*,TARGET <oracle_user_name>.*;
MAPEXCLUDE <exclude_filter>;
--MAP CFG_DB.* #exception_handler();
```

---

## dnscmd Scripts

### Switch to SECONDARY Master Server

```
rem DNSCMD DELETE command
dnscmd 135.17.36.102 /RecordDelete mst.lab cfgmaster A /f
rem DNSCMD ADD command
dnscmd 135.17.36.102 /RecordAdd mst.lab cfgmaster A 135.17.36.140
```

### Switch to MAIN Master Server

```
rem DNSCMD DELETE command
dnscmd 135.17.36.102 /RecordDelete mst.lab cfgmaster A /f
rem DNSCMD ADD command
dnscmd 135.17.36.102 /RecordAdd mst.lab cfgmaster A 135.17.36.139
```

### Switch over Script

```
ipconfig /flushdns
ping cfgmaster.mst.lab
```