

GENESYS

This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Genesys Intelligent Automation Help

Question Block

Contents

- 1 Question Block
 - 1.1 Adding this block to the callflow
 - 1.2 Standard Grammar settings
 - 1.3 Using the Grammar Builder
 - 1.4 Using multiple retry and timeout prompts
 - 1.5 Using recovery modes
 - 1.6 Using rich media with this block

Question Block



Important

Only users with the role **Application Designer** can add **Question** blocks to a callflow. However, both **Application Designer** and **Application Maintainer** roles can view and update **Question** block properties.

You can use **Question** blocks to ask complex questions to callers, such as credit card numbers, dates, or currency amounts. Whereas Menu blocks tend to ask simple questions with limited answers (for example "yes" or "no"), **Question** blocks can use grammars (standard or customized) to specify the format of expected answers. A grammar defines the acceptable words, phrases, commands, or even sentences that the **Question** block accepts as valid input.

Important

Contact your Genesys representative for more information on grammars written in SRGS.

As it might not be possible to create paths from your **Question** block to cover every distinct answer from a caller, Genesys recommends you use a default **success** path to accommodate all successful recognitions (unless a path exactly matches the recognized answer).

Adding this block to the callflow

To add and configure Question blocks on a callflow:

- 1. Drag and drop the **Question** block onto the appropriate position in the callflow.
- 2. Click the **Question** block to open its properties.
- 3. In the **Vocabulary** tab, click the **Mode** menu and select the type of grammar you want to use. You can choose from:
 - Standard Grammar Use a built-in grammar. You can select options such as date or credit card number.
 - Grammar Builder Define a custom simple grammar format. For example, if the Standard Grammar option does not have an option to cover your particular business need, you can use the Grammar Builder option to build your own solution. For example, you can define a grammar that

accepts two digits followed by two to five letters.

Important

For more details, refer to Using the Grammar Builder, below.

• Upload Custom Grammar – Upload a SRGS XML grammar file(s). For example, you could set up a Question block that asks callers for a complex account number that contains a check digit or a small number of possible alpha characters. This can help to ensure better recognition accuracy. You can upload a new voice grammar as well as a DTMF grammar.

Important

- See the Standard Grammar settings section below for more information on standard grammars.
- Contact your Genesys representative for information on the exact format of the SRGS XML grammar file to use.

You might choose to upload both a DTMF grammar and a voice grammar to ensure either response is properly recognized. For example, if the caller speaks their account number and the speech recognizer does not understand what was said, the caller can choose to enter DTMF digits instead.

- 4. In the **Prompts** tab, add prompts for **Initial**, **Retry**, **Timeout**, and **Help**. These prompts can contain references to variables. See the Menu block page for more information on prompts.
- (Optional) In the Questions Options tab, select the Store Answer as a Variable check box if you want to store any answer provided by the caller as a variable. See the Menu block page for more information on working with variables.
- 6. Click **Update**.

Standard Grammar settings

This section explains the settings available for the Standard Grammars.

Important

Intelligent Automation supports masking user input entries in Visual IVR applications from 9.0.111.x version onwards. If the **Confidential Mode** setting is enabled, Visual IVR masks the strings instead of displaying the actual information. This setting does not mask the currencies, dates, numbers, and phone number grammar types.

Credit Card Expiry

Parameter	Description		
MinAllowed	The minimum number of months for which a credit card expiry date can be out of date. The default is -36 , which is three years ago.		
MaxAllowed	The maximum number of months for which a credit card expiry date can be in the future. The default is 36 , which is three years from the current date.		

Credit Card Number

This grammar allows you to specify the types of credit cards that can be accepted from a caller. Setting a type of credit card to **true** allows it to be used; setting a type to **false** disables it.

Currency EUR and Currency GBP

Parameter	Description		
MinAllowed	The absolute minimum amount in Euros/Pounds that can be accepted from a caller.		
MinExpected	The minimum amount of Euros/Pounds expected from a caller. If an amount does not fall between this value and the MaxExpected amount, the speech-recognition engine assigns it a higher confidence score.		
MaxExpected	The maximum amount of Euros/Pounds expected from a caller. If an amount does not fall between this value and the MinExpected amount, the speech-recognition engine assigns it a lower confidence score.		
MaxAllowed	The absolute maximum amount in Euros/Pounds that can be accepted from a caller.		

Date

Parameter	Description
MinAllowed	The absolute minimum number of days before the current date that a date given by a caller can be accepted (for example, input -365 for a year before the current date).
MinExpected	The earliest date expected from a caller. Any date between this value and the MaxExpected date

Parameter	Description		
	results in the speech-recognition engine assigning a high confidence score.		
MaxExpected	The latest date expected from a caller. Any date between this value and the MinExpected date results in the speech-recognition engine assigning a high confidence score.		
MaxAllowed	The absolute maximum number of days after the current date that a date given by a caller can be accepted.		
AllowAmbiguousCentury	Specify whether to accept the century portion of a date from a caller. For example, for the year 2012, a caller may say "twenty-twelve", "two-thousand and twelve," or omit the century completely.		
AllowAmbiguousYear	Specify whether to accept the year portion of a date from a caller. This allows a caller to use a two- digit year or four-digit year for dates after the year 2000. For example, a caller might say "twenty twelve" or "two thousand and twelve."		
DateFormat	Specify the date format. Starting from 9.0.110.23 release, Question blocks now support the YMD, DMY, and MDY date formats.		

Natural Numbers

Natural numbers are positive integers, such as 1, 2, 3, and so on.

Parameter	Description
MinAllowed	The absolute smallest natural number that can be accepted from a caller.
MinExpected	The smallest natural number expected from a caller. Any amount between this value and the MaxExpected number results in the speech-recognition engine assigning a high confidence score.
MaxExpected	The maximum natural number expected from a caller. Any amount between this value and the MinExpected number results in the speech-recognition engine assigning a high confidence score.
MaxAllowed	The absolute highest natural number that can be accepted from a caller.

Phone Number Republic of Ireland (RoI) and Phone Number UK

Parameter	Description
AllowMobiles	Specifies whether a Rol/UK mobile number provided by the caller can be accepted.

Parameter	Description
AllowLandlines	Specifies whether a Rol/UK landline number provided by the caller can be accepted.

Postcode UK

This grammar allows you to specify that only UK-based postcodes can be accepted from the caller.

Time

Parameter	Description
Assume24Hour	Specifies that all times given by callers will be in 24-hour-clock time. For example, when set to true , if a caller says "eight thirty", the speech-recognition engine assume this to mean 8:30 a.m. rather than 8:30 p.m.
MinAllowed	The earliest time that will be accepted from a caller.
MinExpected	The earliest time expected from a caller. Any time between this and the MaxExpected time results in the speech-recognition engine assigning a high confidence score.
MaxExpected	The latest time expected from a caller. Any time between this and the MinExpected time results in the speech-recognition engine assigning a high confidence score.
MaxAllowed	The latest time that will be accepted from a caller.

Sample Grammar Snippet

```
<?xml version="1.0" encoding="UTF-8"?>
<grammar
xml:lang="en-us"
mode="voice"
tag-format="semantics/1.0"
version="1.0"
xmlns="http://www.w3.org/2001/06/grammar"
root="root">
<rule id="root" scope="public">
        <one-of>
            <item>
                <one-of>
                    <item>1</item>
                </one-of>
                <tag>
                    out.MEANING = 'mango';
                    out.dm_confirmation_mode = 'NEVER';
                    out.dm confirm string = '';
                    out.IsFullConfirmationPrompt = true;
                    out.SlotData = '';
                </tag>
            </item>
```

</one-of> </rule>

</grammar>

Parameter	Description		
xml:lang	The language code for the XML. This could be 'en- us' or 'en-gb'.		
mode	The type of input that the user agent should be detecting. The default mode is "voice" for speech recognition grammars. An alternative is 'dtmf'.		
tag-format	The tag-format identifier that indicates the content type of all rule tags and header tags contained within a grammar. Set it to 'semantics/1.0'.		
version	The version number of the grammar element indicates which version of the grammar specification is being used — '1.0'. The grammar version is a required attribute.		
xmlns	The XML namespace being used. This is a required parameter.		
root	The root rule of the grammar. This must be in lowercase.		
out.MEANING	The output generated based on the user input.		
	Specify if a user confirmation is required for the phrase or option collected. The possible options are:		
	 'NEVER' would not ask for a confirmation. 		
out.dm_confirmation_mode	 'ALWAYS' would always ask for a confirmation regardless of the confidence levels. 		
	 'IF_NECESSARY' would ask for a confirmation if the response falls below the high confidence threshold, but above the low threshold, for voice recognition. 		
out.dm_confirm_string	This message is played dependent on the confirmation mode setting.		
out.IsFullConfirmationPrompt	Used to confirm that the system has correctly recognized the answer provided by the caller		
out.SlotData	Defines the slot that matches the phrase. For example, 'expiry date' could be defined as the slot data when requesting credit card information.		

Using the Grammar Builder

The **Grammar Builder** option allows you to define your own simple grammar format. For example, you can set up a grammar for a customer account number that contains a specific mixture of letters, dashes and numbers. Consider the following grammar:

a bescription						
cabulary Prom	pts Qu	estion	Options	Preferences		
ammar Selection						
ode Frammar Builder	•					
Rule	Lower		Upper	Туре	Words [One / Line]	Action
Ask for between	0	and	1	Letters v		
followed by between	1	and	1	Digits •		Delete
followed by between	0	and	1	Words (specify) ▼	hyphen dash	Delete
followed by between	3	and	3	Digits •		Delete

Using the rules in the previous example, the custom grammar accepts any of the following phrases from a caller:

- "B nine four five six"
- "B nine dash four five six"
- "B nine hyphen four five six"
- "nine four five six"
- "nine dash four five six"

• "nine hyphen four five six"

To use the **Grammar Builder** option:

- 1. In the **Lower** field, enter the minimum amount of digits, letters, or words that a caller must provide. If caller does not need to provide a response for this rule, enter 0 in this field.
- 2. In the **Upper** field, enter the maximum number of digits, letters, or words that the caller must provide.

In the example above, the rule specified that the caller must provide between **0** and **1** letters. In other words, the caller might provide a letter, or not. If you do require the caller to provide one letter only, set the **Lower** and **Upper** values to 1 and 1, respectively.

- 3. In the **Type** menu, select from the following:
 - Digits
 - Non-Zero Digits
 - Letters
 - Digits or Letters
 - Words (specify) If selected, enter the words that this grammar accepts. For example, dash or hyphen. The grammar might recognize these words, but they are not included in the final result. Therefore, if the caller says, "one two dash four", a result of "124" is recognized.
- 4. (Optional) To add another rule, click Add Rule.
- 5. Click **Update** to save the grammar.

Using multiple retry and timeout prompts

Important

- You must have the Application Designer role, or higher, to use this feature. If you are not using standard roles, you must have the configure_number_entry_retry_timeout_prompts permission.
- The availability of this feature is dependent on whether:
 - In Default Server Settings, the setting **Prompts.RetryTimeout.MaxAllowed** has a value greater than 1 (as of the 9.0.101.00 release, the default value is 2).
 - In the application or module details page, the **Allowed number of retry/timeout prompts** has a value greater than **1**.

In some situations, you might want to offer different iterations of a retry or timeout prompt to assist the caller. For example:

• Caller inputs incorrect information.

- Retry 1: "Please try again."
- Caller inputs incorrect information.
- *Retry 2*: "It looks like we are having trouble with your response. Press 0 to speak with an agent for assistance."

If properly configured (see note above), you can add multiple retry and timeout prompts to this block by clicking **Show more retry prompts** or **Show more timeout prompts** to see the additional prompts.

If the callflow requires additional retry or timeout prompts, Intelligent Automation repeats the last prompt. For example, if your environment supports three retry prompts and the caller requires a fourth retry attempt, the third retry prompt will repeat for all additional retries.

Using recovery modes

When the recovery options are configured in the **VUI Preferences** page and the block's maximum tries count is reached, the recovery mode is enabled and a recovery prompt is played asking the user to confirm if the callflow is to be transferred to an agent (DTMF *) or if the block is to be reprocessed (DTMF 1).

- Recovery mode enabled This setting enables or disables the recovery option mechanism on the specific block.
- **Recovery barge-in enabled** This setting enables or disables the barge-in option for the upcoming recovery option prompt.
- **Recovery 'try again' menu option DTMF** This setting allows configuring a different DTMF value. The default value, DTMF 1 is used for the 'try again' option.
- **Recovery 'agent' menu option DTMF** This setting allows configuring a different DTMF value. The default value, DTMF * is used for the agent transfer option.

Name		Value	
Recovery mode enabled	~	True 🗸	Delete
Recovery barge-in enabled	~	True 🗸	Delete
Recovery 'agent' menu option DTMF	~	*	Delete
Recovery 'try again' menu option DTMF	~	1	Delete

Using rich media with this block

If you are using a chat-based Persona, you can add rich media elements to this block by selecting the **Show Rich Media Editor** checkbox, which displays a new section called **Rich Media Editor** below the **Initial** prompt.

Enter the following information:

- Image—Enter a URL for an image, or click Upload a File to upload an image from your computer.
- Video—Enter a URL for a video, or click Upload a File to upload a video from your computer. To display a static image before the user plays the video, you must also enter a URL in the Image field.



- **Description**—Enter description text that appears below the **Header** text.
- Submit Button Text—This field is not currently supported.
- Web URLs—Enter a web URL that the customer can select to get more information. It must be in this format: [link:URL;Description]. For example: [link:https://www.genesys.com;Genesys]. In the preceding example, *https://www.genesys.com* is the URL that opens if the button is selected, and *Genesys* is the name of the button or link that the customer must select to open the URL.

Important The appearance of certain elements, such as **Web URL**, depends on the **Rich Media Format** callflow preference. For example, the **Text Only** format displays links as text, but **Text and Buttons** displays links as buttons.

The following graphic shows how each element might appear in a typical chat widget. Your chat widget might appear differently, depending on your environment's configuration and style rules.



Important

Some users can also set callflow preferences and default server settings to configure how Intelligent Automation processes rich media. See the Setting Callflow Preferences page for more information.

For more information about rich media functionality, refer to the Rich Media page in this manual.