



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Genesys Mobile Services Deployment Guide

Migrating GMS 8.1.x to 8.5

Contents

- 1 Migrating GMS 8.1.x to 8.5
 - 1.1 GMS Cluster Application Configuration
 - 1.2 GMS Cluster Migration (Cassandra)
 - 1.3 Service Migration
 - 1.4 Notification
 - 1.5 Chat
 - 1.6 Port Configuration

Migrating GMS 8.1.x to 8.5

GMS Cluster Application Configuration

In order to deploy Genesys Mobile Services (GMS) 8.1.x, a specific application had to be created for each GMS, and then each application had to be configured with the same options.

The GMS 8.5 release introduces a new deployment model; a single Application Cluster object that can be configured for a cluster of GMS's. Each GMS requires its own GMS application in Configuration Manager, which includes a link to the Application Cluster Object in its Connection tab. This enables grouping the common options into a single place. See [Creating an Application Object](#) for more information about this deployment model.

GMS Cluster Migration (Cassandra)

For a cluster of three nodes:

1. Stop one of the GMS 8.1.x nodes. This can be either a seed-node, or non seed-node.
2. Create a new GMS application using the GMS 8.5 template (see the [deployment instructions](#)).
3. Install GMS 8.5.
4. Start GMS 8.5. GMS 8.5 synchronizes with the other GMS 8.1.1 nodes in the cluster.
5. Repeat these steps for all of the GMS 8.1.x nodes. When complete, the cluster is upgraded to GMS 8.5 with data from the GMS 8.1.x cluster.

Service Migration

Starting in GMS 8.1.2, default service options are prefixed with an underscore (_). The following shows an example migration:

8.1.1

[service.match-interaction]

Option	Value
delete_match	true
service	match-interaction
type	builtin

8.5

[service.match-interaction]

Option	Value
_service	match-interaction
_type	builtin

Parameters that begin with an underscore (_) are passed to ORS. Anything else is considered user data, and saved in storage. The stored data can be retrieved using the `_data_id` parameter passed in scxml.

Notification

Google has deprecated the C2DM Service, and no new users are being accepted; however, apps using C2DM will continue to work. For more information, see the [Android Cloud to Device Messaging Framework](#) documentation.

For customers that want to send notifications to Android devices, using the GCM notification provider is encouraged.

Note that you do not need to prefix options with an underscore.

Chat

Existing 8.1.x Chat service will continue to work with GMS 8.5. Chat service options must be migrated according to the preceding [Service Migration](#) section. Genesys recommends migrating to Callback Chat service as defined in the [Callback User's Guide](#).

Port Configuration

Important

This section applies to GMS 8.5.104 and higher.

Because of the port restriction feature introduced in GMS 8.5.001, the GMS HTTP port is no longer configured in the GMS `<GMS_HOME>/launcher.xml` file. To configure HTTP port(s), you must add the HTTP connector into the `<GMS_HOME>/etc/jetty-http.xml` file:

```
<Call name="addConnector">
  <Arg>
    <New class="org.eclipse.jetty.server.ServerConnector">
      <Arg name="server"><Ref refid="Server" /></Arg>
    </New>
  </Arg>
</Call>
```

```
<Arg name="acceptors" type="int"><Property name="http.acceptors" default="-1"/></Arg>
<Arg name="selectors" type="int"><Property name="http.selectors" default="-1"/></Arg>
<Arg name="factories">
  <Array type="org.eclipse.jetty.server.ConnectionFactory">
    <Item>
      <New class="org.eclipse.jetty.server.HttpConnectionFactory">
        <Arg name="config"><Ref refid="httpConfig" /></Arg>
      </New>
    </Item>
  </Array>
</Arg>
<Set name="host"><Property name="jetty.host" /></Set>
<Set name="port"><Property name="jetty.port" default="*8080*" /></Set>
<Set name="idleTimeout"><Property name="http.timeout" default="30000"/></Set>
<Set name="soLingerTime"><Property name="http.soLingerTime" default="-1"/></Set>
<Set name="acceptorPriorityDelta"><Property name="http.acceptorPriorityDelta"
default="0"/></Set>
<Set name="selectorPriorityDelta"><Property name="http.selectorPriorityDelta"
default="0"/></Set>
<Set name="acceptQueueSize"><Property name="http.acceptQueueSize" default="0"/></Set>
  </New>
</Arg>
</Call>
```