

GENESYS

This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Genesys Engage Digital (eServices)

MSMQ-MQSeries Event Logger DAP

MSMQ-MQSeries Event Logger DAP

Event Logger can send events to a message queue. This provides a mechanism for reliable delivery of reporting events to Interaction Server's reporting clients. Disconnection of the client does not lead to a loss of reporting events. Instead, events are preserved for the specific client and delivered to the client (or otherwise read by the client) after its restart. The message queue requires a DAP object that is specifically for streaming reporting events to that message queue.

These options are configured on the DAP for a IBM MQ-Series or Microsoft Message Queue (MSMQ) queue.

event-filtering Section

· event-filter-by-id

event-filter-by-id

Default Value: No default value

Valid Values: Comma-separated list of event identifiers

Changes Take Effect: Immediately Related Options: event-filter-by-id

If this option is present and not empty, only events with event IDs specified in the comma-separated list and permitted by the event type filters are logged into their corresponding reporting tables. If this option is absent or empty, all events permitted by the event type filters are logged into their corresponding reporting tables.

logger-settings Section

delivery-protocol

name

recoverable

- delivery-queue-manager-
- delivery-queue-name
- udata

delivery-protocol

Default Value: eventlog

Valid Values: mq-series, msmq, eventlog, jms

Changes Take Effect: After restart

Specifies the delivery protocol to be used for Event Logging.

delivery-queue-manager-name

Default Value: No default value

Valid Values: Any valid queue manager name

Changes Take Effect: After restart Related Options: delivery-queue-name

This option is used for logging events to MQ-Series message queues. MQ-Series message queues have a queue manager entity that manages a set of message queues. To post messages to an MQ-Series queue the queue manager name and a queue name (see delivery-queue-name) should be specified.

delivery-queue-name

Default Value: No default value **Valid Values:** Any valid queue name **Changes Take Effect:** After restart

Specifies the name of the queue to which messages will be sent. For MSMQ or MQ-Series, this specifies the name of the queue.

recoverable

Default Value: false **Valid Values:** true, false

Changes Take Effect: Immediately

If this option is set to true, the messages being sent will have a flag MQMSG_DELIVERY_RECOVERABLE, otherwise, the messages will have a flag MQMSG_DELIVERY_EXPRESS.

udata

Default Value: No default value

Valid Values: Comma-separated list of event identifiers

Changes Take Effect: Immediately

Specifies a comma-separated list of event identifiers which must contain user data. If the option is absent or empty, that is interpreted to mean that all user data is to be included in all events. This option is analogous to the UData key used in reporting registration.