

# **GENESYS**

This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

# Performance Management Advisors Deployment Guide

Manage Advisors Stat Server Instances

# Manage Advisors Stat Server Instances

Starting in release 8.5.1, Stat Server registration is no longer done during deployment. Previously, you input Stat Server connection information in installer screens, which registered the Stat Servers. You now execute dedicated database procedures against the Advisors Platform database to:

- · register or remove Stat Server instances
- · add, edit, or remove Stat Server configuration settings related to Advisors

Performance Management Advisors include two stored procedures that you use to perform the preceding tasks:

- SPSTATSERVERCONFIG
- SPCHANGEOBIDISTRIBUTION

## Microsoft SQL Server Database Procedures

If you have a Microsoft SQL Server database environment, you can use the spStatServerConfig and spChangeObjDistribution database procedures and parameters as shown in the examples for an Oracle environment, but replace the syntax to execute the stored procedures. MS SQL Server syntax is shown below.

## MS SQL Server Syntax for spStatServerConfig

```
DECLARE @r int.
@m varchar(4000);
EXEC spStatServerConfig
@p_SsPairId = null,
@p ModuleCode = N'CCAdv',
@p AdapterId = 1,
@p_StatServerHost = N'statserverhost.company.com',
@p_StatServerPort = 7002,
@p_StatServerName = N'SS812-68',
@p_StatServerDescr = N'CCAdv core stats',
@p Core = 1,
@p MultiMedia = 0,
@p_ThirdPartyMedia = 0,
@p_StatServerBackHost = NULL,
@p StatServerBackPort = NULL,
@p_StatServerBackName = NULL,
ar = ar OUTPUT,
@m = @m OUTPUT;
SELECT @r as N'@r',
@m as N'@m';
```

### MS SQL Server Syntax for spChangeObjDistribution

```
DECLARE @r int, @m varchar(255);
EXEC spChangeObjDistribution

@p_SsPairId_old = <original stat server pair id>, --from

@p_SsPairId_new = <target stat server pair id>, --to

@p_ModuleCode='CCAdv',

@r = @r OUTPUT,

@m = @m OUTPUT;

SELECT @m;
```

# Oracle Database Example Procedures

Use the SPSTATSERVERCONFIG and SPCHANGEOBJDISTRIBUTION database procedures and parameters as shown in the following examples.

The following examples show you how to use the stored database procedures to manage your Advisors Stat Server configuration if you use an Oracle environment, but the MS SQL Server procedures use the same parameters and processes:

- Register a New Stat Server and Link the Stat Server to an Adapter
- Change the Connection Properties of the Stat Server
- Add New Statistic Types to the Existing Stat Server
- Remove Stat Server Statistic Type Assignments
- Re-distribute the Statistics Load when Stat Servers are Added

#### Register a New Stat Server and Link the Stat Server to an Adapter

The following procedure uses CCAdv (Contact Center Advisor) for the module code. For Frontline Advisor, use the same procedure, but enter FA for the module code.

# Procedure: Registering a Stat Server and Linking the Stat Server to the CCAdv Adapter

**Purpose:** In this example, the CCAdv adapter has id=1. The procedure instructs Stat Server to process only core statistics.

#### Steps

1. Call the procedure:

```
SET SERVEROUTPUT ON
SET FEEDBACK OFF
DECLARE
R NUMBER:
M VARCHAR2 (4000);
BEGIN
SPSTATSERVERCONFIG(
P SSPAIRID => NULL,
P_MODULECODE => 'CCAdv',
P_ADAPTERID =>1,
P_STATSERVERHOST => 'statserverhost.company.com',
P STATSERVERPORT => 7002.
P STATSERVERNAME => 'SS812-68',
P_STATSERVERDESCR => 'CCAdv core stats',
P_CORE => 1,
P_MULTIMEDIA => 0,
P THIRDPARTYMEDIA => 0,
P STATSERVERBACKNAME => NULL,
P STATSERVERBACKHOST => NULL,
P_STATSERVERBACKPORT => NULL,
R => R,
M => M
END;
```

Change the Connection Properties of the Stat Server

# Procedure: Changing the Stat Server Connection Properties

**Purpose:** This example changes the connection properties of the Stat Server added in the first example above.

#### Steps

1. Determine the Stat Server pair ID:

```
SELECT SS PAIR ID FROM STAT SERVER INSTANCES WHERE NAME='SS812-33';
```

2. In this example, assume the Stat Server pair ID is 5. Call the procedure:

```
SET SERVEROUTPUT ON
SET FEEDBACK OFF
DECLARE
R NUMBER;
M VARCHAR2 (4000);
BEGIN
SPSTATSERVERCONFIG(
P_SSPAIRID => 5,
P_MODULECODE => 'CCAdv',
P_ADAPTERID =>1,
P STATSERVERHOST => 'statserverhost2.company.com',
P_STATSERVERPORT => 7003,
P_STATSERVERNAME => 'SS812-70'
P_STATSERVERDESCR => 'CCAdv core stats',
P_CORE => 1,
P MULTIMEDIA => 0.
P THIRDPARTYMEDIA => 0,
P_STATSERVERBACKNAME => NULL,
P_STATSERVERBACKHOST => NULL,
P_STATSERVERBACKPORT => NULL,
R => R,
M => M
);
END:
```

### Add New Statistic Types to the Existing Stat Server

# Procedure: Adding new Statistic Types to a Registered Stat Server

**Purpose:** In this example, the procedure adds the multimedia statistic type.

#### Steps

1. Determine the Stat Server pair ID:

```
SELECT SS_PAIR_ID FROM STAT_SERVER_INSTANCES WHERE NAME='SS812-33';
```

2. In this example, assume the Stat Server pair ID is 5. Call the procedure:

```
SET SERVEROUTPUT ON
SET FEEDBACK OFF
DECLARE
R NUMBER;
```

```
M VARCHAR2(4000);

BEGIN
SPSTATSERVERCONFIG(
P_SSPAIRID => 5,
P_MODULECODE => 'CCCAdv',
P_ADAPTERID =>1,
P_STATSERVERHOST => 'statserverhost2.company.com',
P_STATSERVERPORT => 7003,
P_STATSERVERNAME => 'SS812-70',
P_STATSERVERNAME => 'CCAdv core stats',
P_CORE => 1,
P_MULTIMEDIA => 1,
P_THIRDPARTYMEDIA => 0,
P_STATSERVERBACKNAME => NULL,
P_STATSERVERBACKHOST => NULL,
P_STATSERVERBACKHOST => NULL,
R => R,
M => M
);
END;
//
```

#### Remove Stat Server Statistic Type Assignments

# Procedure: Removing Stat Server Statistic Type Assignments

**Purpose:** In this example, the procedure removes multimedia and third party media statistic types.

#### Steps

1. Determine the Stat Server pair ID:

```
SELECT SS_PAIR_ID FROM STAT_SERVER_INSTANCES WHERE NAME='SS812-33';
```

2. In this example, assume the Stat Server pair ID is 5. Call the procedure; set the parameters to 0 that are associated with statistic types that you want to remove. For example, the following procedure removes multimedia and third party media statistic types:

```
SET SERVEROUTPUT ON
SET FEEDBACK OFF
DECLARE
R NUMBER;
M VARCHAR2(4000);
BEGIN
```

```
SPSTATSERVERCONFIG(
P_SSPAIRID => 5,
P_MODULECODE => 'CCAdv',
P_ADAPTERID =>1,
P_STATSERVERHOST => 'statserverhost2.company.com',
P_STATSERVERPORT => 7003,
P_STATSERVERNAME => 'SS812-70',
P_STATSERVERDESCR => 'CCAdv core stats',
P_CORE => 1,
P_MULTIMEDIA => 0,
P_THIRDPARTYMEDIA => 0,
P_STATSERVERBACKNAME => NULL,
P_STATSERVERBACKHOST => NULL,
P_STATSERVERBACKPORT => NULL,
R => R,
M => M
);
END;
/
```

The procedure returns a message depending on the outcome: success, or failure with further instructions.

The failure to remove a statistic type usually occurs when there are already objects associated with the Stat Server and the corresponding statistic type.

If the goal is to move the processing of a statistic type to another Stat Server, then you must move all related objects to the corresponding Stat Server. You can move the objects by executing the following procedure:

```
SET SERVEROUTPUT ON
SET FEEDBACK OFF
DECLARE
P SSPAIRID OLD NUMBER;
P SSPAIRID_NEW NUMBER;
P_MODULECODE VARCHAR2(200);
R NUMBER;
M VARCHAR2 (4000);
BEGIN
P_SSPAIRID_OLD := <original Stat Server pair id>; --from
P SSPAIRID NEW := <target Stat Server pair id>; --to
P_MODULECODE:= NULL;
SPCHANGEOBJDISTRIBUTION(
P_SSPAIRID_OLD => P_SSPAIRID_OLD,
P_SSPAIRID_NEW => P_SSPAIRID_NEW,
P MODULECODE => P MODULECODE,
R \Rightarrow R
M => M
);
COMMIT;
dbms_output.put_line(M);
END;
```

After the objects are moved, execute the SPSTATSERVERCONFIG procedure again using the same parameters you used initially.

#### Remove a Stat Server Record

# Procedure: Removing a Stat Server Record

#### **Prerequisites**

• You must remove Stat Server statistic type assignments (see Remove Stat Server Statistic Type Assignments) before removing a Stat Server record.

#### Steps

- 1. Execute SPSTATSERVERCONFIG to remove all statistic types as explained in Remove Stat Server Statistic Type Assignments. If the procedure returns a failure, do one of the following:
  - a. Move objects to another Stat Server by executing the SPCHANGEOBJDISTRIBUTION procedure as explained in Remove Stat Server Statistic Type Assignments. After objects have been moved to another Stat Server, execute SPSTATSERVERCONFIG again using the same parameters you used initially.
  - Force object deletion. In this case, object distribution will be done automatically by the Advisors Genesys Adapter when it starts or during the overnight update.
     To force object deletion, execute the SPCHANGEOBJDISTRIBUTION procedure with stat type parameters set to -1:

```
SET SERVEROUTPUT ON
SET FEEDBACK OFF
DECL ARE
R NUMBER;
M VARCHAR2 (4000);
SPSTATSERVERCONFIG(
P_SSPAIRID => 5 ,
P_MODULECODE => 'CCAdv',
P ADAPTERID =>1,
P STATSERVERHOST => 'statserverhost2.company.com',
P STATSERVERPORT => 7003,
P_STATSERVERNAME => 'SS812-70',
P_STATSERVERDESCR => 'CCAdv core stats',
P_CORE => -1 ,
P MULTIMEDIA => -1,
P THIRDPARTYMEDIA => -1,
P STATSERVERBACKNAME => NULL,
P_STATSERVERBACKHOST => NULL,
P_STATSERVERBACKPORT => NULL, R => R,
M => M
);
END;
```

2. Execute a simple delete statement to remove the Stat Server instance:

```
DELETE STAT_SERVER_INSTANCES WHERE SS_PAIR_ID=<the id of the Stat Server to be
deleted>;
COMMIT;
```

#### Re-distribute the Statistics Load when Stat Servers are Added

The relationship between a statistic and the Stat Server pair against which it is requested is maintained. This means that after a start, restart, or refresh of the adapter, each adapter continues to request statistics from the same Stat Server(s) from which it requested stats before the restart. AGA no longer depends on the value set for the Stat Server old-stats-remove-interval option.

If any additional Stat Servers are added after the initial starting of the adapters, the statistics already requested from existing Stat Servers are not automatically re-distributed to the newly added Stat Server pair. The following procedures describe two scenarios in which you would re-distribute the statistics load on the Advisors Stat Servers. See:

- Moving Statistics of a Specific Type to a New Stat Server
- Evenly Distributing Stats Load After Adding a New Stat Server

# Procedure: Moving Statistics of a Specific Type to a New Stat Server

**Purpose:** In this example, you have a Stat Server configured to process core and multimedia statistics. You decide to add a Stat Server to handle only multimedia statistics. You will move all multimedia processing to the new Stat Server.

#### Steps

- 1. Stop the Advisors server, all Advisors Genesys Adapters, and XML Generator.
- 2. Register a new Stat Server.
- 3. Detemine the SS\_PAIR\_ID of each Stat Server:

```
P_SSPAIRID_OLD,P_SSPAIRID_NEW
SELECT SS_PAIR_ID,NAME FROM STAT_SERVER_INSTANCES;
```

4. Execute the SPCHANGEOBJDISTRIBUTION procedure:

```
SET SERVEROUTPUT ON
   SET FEEDBACK OFF
   DECLARE
   P_SSPAIRID_OLD NUMBER;
P_SSPAIRID_NEW NUMBER;
   P_MODULECODE VARCHAR2(200);
   R NUMBER;
   M VARCHAR2(4000);
   P SSPAIRID OLD := <original stat server pair id>; --from
   P SSPAIRID NEW := <target stat server pair id>; --to
   P MODULECODE := NULL;
   SPCHANGEOBJDISTRIBUTION(
   P_SSPAIRID_OLD => P_SSPAIRID_OLD,
P_SSPAIRID_NEW => P_SSPAIRID_NEW,
   P MODULECODE => P MODULECODE,
   R => R,
   M => M
    );
   COMMIT;
   dbms_output.put_line(M);
   END;
5. To ensure that no multimedia statistics are ever distributed to your original Stat Server again,
   disassociate the multimedia statistic type from that Stat Server:
   SET SERVEROUTPUT ON
   SET FEEDBACK OFF
   DECLARE
   R NUMBER;
   M VARCHAR2 (4000);
   BEGIN
   SPSTATSERVERCONFIG(
   P_SSPAIRID => 5 ,
P_MODULECODE => 'CCAdv', --mandatory if P_ADAPTERID is not supplied
   P ADAPTERID =>1, --mandatory if P MODULECODE is not supplied
   P_STATSERVERHOST => 'statserverhost2.company.com',
   P_STATSERVERPORT => 7003,
P_STATSERVERNAME => 'SS812-70',
P_STATSERVERDESCR => 'CCAdv core stats',
   P^{-}CORE \Rightarrow 1,
   P MULTIMEDIA => 0,
   P_THIRDPARTYMEDIA => 0,
P_STATSERVERBACKNAME => NULL,
   P STATSERVERBACKHOST => NULL,
   P STATSERVERBACKPORT => NULL,
   R => R,
   M => M
    );
   END;
```

6. Start all Advisors Genesys Adapters, XML Generator, and the Advisors server.

# Procedure: Evenly Distributing Stats Load After Adding a New Stat Server

**Purpose:** In this example, you have a Stat Server configured to process one or more statistic types. You decide to add another Stat Server to process the same statistic types. You will distribute the statistics load evenly between the two Stat Servers and not separate the statistic type processing.

In this scenario, it is best to initiate the automatic statistic load distribution.

#### Steps

- 1. Stop the FA Server, all Advisors Genesys Adapters, and, for CCAdv, XML Generator.
- 2. Connect to the platform database.
- 3. Remove all entries from STAT\_GROUP\_OBJ\_MAPPING, and commit the changes:
  - Oracle:

```
DELETE STAT_GROUP_OBJ_MAPPING;
COMMIT:
```

MSSQL:

```
BEGIN TRANSACTION;
DELETE STAT_GROUP_OBJ_MAPPING;
COMMIT TRANSACTION;
```

- 4. Restart all stopped components:
  - For CCAdv: Restart all CCAdv adapter servers and XML Generator.
  - For FA adapters: Restart all FA adapter servers and the FA Server.