

GENESYS

This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Reporting and Analytics Aggregates Physical Data Model for an Oracle Database

Table AGT SDR BOT HOUR

Table AGT_SDR_BOT_HOUR

Description

Introduced: 9.0.001.03

In partitioned databases, this table is not partitioned.

This disposition-based aggregate table provides a rollup of interactions involving bots, and associated with Designer applications.

Tip

- This document shows table information because it is more informative than view information. However, directly querying tables is not supported; perform your queries on views.
- This document shows the HOUR structure for each table, as an example. For each table, the same structure is used for SUBHR through YEAR views.
- · Where referenced, IRF resources include:
 - Handling resources (such as self-service IVR ports, agents, or non-agent-associated DNs)
 - Mediation resources (such as a non-self-service IVR ports, voice treatment ports, ACD queues, routing points, and so forth) where the interaction ends in mediation before being distributed to a handling resource.
- IRF is an abbreviation for the INTERACTION_RESOURCE_FACT table.
- MSF is an abbreviation for the MEDIATION_SEGMENT_FACT table.

Tip

To assist you in preparing supplementary documentation, click the following link to download a comma-separated text file containing information such as the data types and descriptions for all columns in this table: Download a CSV file.

Hint: For easiest viewing, open the downloaded CSV file in Excel and adjust settings for column widths, text wrapping, and so on as desired. Depending on your browser and other system settings, you might need to save the file to your desktop first.

Column List

Legend

Column	Data Type	Р	M	F	DV
DATE_TIME_KEY	NUMBER(38,0)			X	-1
SDR_CALL_TYPE_	KNWMBER(38,0)		X	X	-2
SDR_ENTRY_POIN	NTN_MMBER(38,0)		X	X	-2
SDR_APPLICATIO	N <u>N</u> KAMBER(38,0)		X	X	-2
SDR_GEO_LOCAT	1000 MBER(38,0)		Χ	X	-2
SDR_LANGUAGE_	MEMMBER(38,0)		Χ	X	-2
BOT_ATTRIBUTES	MEMBER(10)		Χ	X	-2
BOT_INTENT_KEY	NUMBER(10)		Χ	X	-2
LAST_BOT_INTEN	TNKEYBER(38,0)		Χ	X	-2
AGR_SET_KEY	NUMBER(38,0)		Χ	X	-1
ENTERED	NUMBER(38,0)				
SS_ENTERED	NUMBER(38,0)				
SS_BOTS_ENTERI	ENUMBER(38,0)				
SS_DURATION	NUMBER(38,0)				
SS_BOTS_DURAT	ONUMBER(38,0)				
BOT_ENTERED	NUMBER(38,0)				
BOT_SUCCESS	NUMBER(38,0)				
BOT_FAILED	NUMBER(38,0)				
INTENTS	NUMBER(38,0)				
INTENTS_DURATI	ONUMBER(38,0)				
LAST_INTENTS	NUMBER(38,0)				
SS_ABANDONED	NUMBER(38,0)				
QUEUE_ABANDONNDMBER(38,0)					
AGENT_ROUTED	NUMBER(38,0)				
DN_ROUTED	NUMBER(38,0)				

DATE TIME KEY

The surrogate key that is used to join this aggregate table to the DATE_TIME dimension table to identify the calendar date and 15-minute interval at which the agent's participation in the interaction began.

SDR_CALL_TYPE_KEY

The key that is used to join the SDR CALL TYPE dimension to the fact tables.

SDR_ENTRY_POINT_KEY

The key that is used to join the SDR ENTRY POINT dimension to the fact tables.

SDR APPLICATION KEY

The key that is used to join the SDR_APPLICATION dimension to the fact tables.

SDR GEO LOCATION KEY

The key that is used to join the SDR GEO LOCATION dimension to the fact tables.

SDR_LANGUAGE_KEY

The key that is used to join the SDR LANGUAGE dimension to the fact tables.

BOT_ATTRIBUTES_KEY

The key that is used to join the BOT ATTRIBUTES dimension to the fact tables.

BOT_INTENT_KEY

The ID of a recognized BOT intent.

LAST_BOT_INTENT_KEY

The ID of the last recognized BOT intent.

AGR SET KEY

The surrogate key that is used to join this aggregate table to the AGR SET table.

ENTERED

The total number of SDR sessions.

SS ENTERED

The total number of SDR sessions in which Self-Service was used.

SS BOTS ENTERED

The total number of Self-Service SDR sessions in which bots participated.

SS_DURATION

The total duration (in seconds) of all Self-Service SDR sessions.

SS BOTS DURATION

The total duration (in seconds) of all Self-Service SDR sessions in which bots participated.

BOT_ENTERED

The total number of bot sessions. If a bot is invoked more than once within a SDR sessions, it is counted more than once.

BOT SUCCESS

The total number of successful bot sessions.

BOT_FAILED

The total number of failed bot sessions.

INTENTS

The total number of customer intents that were recognized. In SDR sessions where more than one intent is recognized, each one is counted.

INTENTS_DURATION

The total amount of time (in seconds) that elapsed for customer intents to be recognized.

LAST INTENTS

The total number of last intents. In SDR sessions where more than one customer intent is recognized, this metric counts the last intent identified.

SS ABANDONED

The total number of interactions that entered the Self-Service phase of the Designer application and were subsequently abandoned in Self-Service. If more than one intent is recognized during an SDR session, this count considers only the last intent.

QUEUE ABANDONED

The total number of interactions that entered the Self-Service phase of the Designer application, requested Assisted-Service, and were subsequently abandoned while waiting in queue. If more than one intent is recognized during an SDR session, this count considers only the last intent.

AGENT ROUTED

The total number of interactions that entered the Self-Service phase of the Designer application and were later routed to an agent. If more than one intent is recognized during an SDR session, this count considers only the last intent.

DN_ROUTED

The total number of interactions that entered the Self-Service phase of the Designer application and were later routed to a DN. If more than one intent is recognized during an SDR sessions, this count considers only the last intent.

Subject Areas

No subject area information available.