



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Genesys Mobile Services Deployment Guide

Basic Authentication

12/17/2025

Contents

- 1 Basic Authentication
 - 1.1 Configuration
 - 1.2 Client Side
 - 1.3 DFM Configuration

Basic Authentication

HTTP Basic Authentication is a method for an HTTP client to provide a user name and a user password for each HTTP request where a resource needs access control.

GMS supports Basic Authentication on the following services:

- Storage service
- Notification service
- and all services that have a section (with the prefix **service.**) in the GMS application

Note: Best practice is to use Basic Authentication over HTTPS.

Configuration


By default, the Basic Authentication feature is turned off. The following sections and options must be set in the GMS application in order to turn on this feature.

Note: Basic Authentication options are taken into account dynamically.

Section	Option	Supersedes	Description
server	realm		Defines the authentication scheme. The default value is Genesys Application Configuration Needed.
server	username		Defines a global username for all services. Note: Without the password option, no authentication is effective.
server	password		Defines a global password for all services. With this option, Basic Authentication is turned on for all services.
service.*	username	server/username	Defines a specific username for one service. Note: Without the password option in the same service section, the server section password is


Section	Option	Supersedes	Description
			used. If there is no server section password, no authentication is applied.
service.*	password	server/password	Defines a specific password for one service.
storage	username	server/username	Defines a specific username for the storage service. Note: Without the password option in the same service section, the server section password is used. If there is no server section password, no authentication is applied.
storage	password	server/password	Defines a specific password for the storage service.
notification	username	server/username	Defines a specific username for the notification service. Note: Without password option in the same service section, the server section password is used. If there is no server section password, no authentication is applied.
notification	password	server/password	Defines a specific password for notification service.

GMS Options for HTTP Basic Authentication




Precedence Example

Example




Configuration Option Examples


Basic Authentication Username and Password for Notification API:




Basic Authentication Username and Password for GMS Node API:



Basic Authentication Username and Password for Service API:



Basic Authentication Username Password for Storage API:



Client Side

When Basic Authentication is turned on from the GMS server-side, the client must manage the HTTP Authentication header to set the username and password in the Authorization header. Only HTTP Basic Authentication is supported. The header request for authentication should look like the following (credential is a string with a specific format [username:password], and base64 encoded):

Request

```
> GET /genesys/1/storage/id HTTP/1.1
> Host: localhost:8080
> Accept: */*
> Authorization: Basic ZGVmYXVsdDpwYXNzd29yZA==
```

Response

```
< HTTP/1.1 200 OK
< Date: Thu, 13 Feb 2014 14:44:14 GMT
```

If the authentication fails, the response looks like this:

Request

```
> GET /genesys/1/storage/id HTTP/1.1
> Host: localhost:8080
```

Basic Authentication

```
> Accept: */*
> Authorization: Basic ZGVmYBVsDpwYXNzd29yZA==
```

Response

```
< HTTP/1.1 401 Unauthorized
< Date: Thu, 13 Feb 2014 14:47:55 GMT
< WWW-Authenticate: Basic realm="Genesys Application Configuration Needed"
< Content-Length: 0
```

Example:

Configuration Manager is configured for the `service.request-interaction` section using the following basic authentication parameters:

- username = genesys
- password = genesys

Request without credential:

```
POST /genesys/1/service/request-interaction HTTP/1.1
Host: localhost:8080
Accept: */*
Content-Length: 40
Content-Type: application/x-www-form-urlencoded
```

Response with the authentication error:

```
HTTP/1.1 401 Unauthorized
Date: Thu, 13 Mar 2014 07:55:38 GMT
WWW-Authenticate: Basic realm="Genesys Application Configuration Needed"
```

The same request with credential:

```
POST /genesys/1/service/request-interaction HTTP/1.1
Authorization: Basic Z2VuZXN5czpnZW5lc3lz
Host: localhost:8080
Accept: */*
Content-Length: 40
Content-Type: application/x-www-form-urlencoded
```

Response of the request:

```
HTTP/1.1 200 OK
Date: Thu, 13 Mar 2014 07:55:55 GMT
Expires: Thu, 01 Jan 1970 00:00:00 GMT
Content-Type: application/json;charset=UTF-8
{"_access_code":"152606","expiration_time":"29","_id":"413-ac85eb82-3e5e-414e-9ed2-08392320f234",
 "_access_number":"6504664630"}
```

DFM Configuration

When using Basic Authentication, you must also update DFM in order to protect the username/

password.

1. In Configuration Manager, locate and open the Application object for your Orchestration Server (ORS).
2. Select the *Options* tab.
3. Add a new section `dfm.<server_name>`.
4. Add the following options and values:
 - username, value = `genesys1`
 - password, value = `password1`
 - maxage, value = 60 (optional)
 - maxstale, value = 60 (optional)
5. Repeat Steps 3 and 4 for each server.
6. Save the ORS application object and restart ORS.

Important

If the username/password is changed in GMS sections (server, storage, notification, service[s]), the username/password must also be changed in ORS DFM accordingly. For example, if you set username/password in server section, you can use the same username/password for all GMS DFM in ORS (if you change the GMS username/password, you must also change it in ORS DFM for GMS). If you set a specific username/password for Service, Storage, or Notification API rather than using the main one (in server section), you must also change the settings in each GMS DFM in ORS in order to manage different username/passwords.