



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Interaction Server Deployment Guide

Migrating to ODBC from DB Server (8.5.3 Only)

12/20/2025

Migrating to ODBC from DB Server (8.5.3 Only)

Starting with release 8.5.3, you must configure Interaction Server to use ODBC database connections. Support for DB Server is deprecated and existing environments must migrate to using ODBC connections.

This page explains how to migrate existing DB Server connections to use ODBC connections.

Important note

Some technical details on the following pages are obsolete and do not apply to Interaction Server 8.5.3:

- [Deploying Interaction Server](#) in the eServices Deployment Guide
- [ODBC Connection](#) in this guide
- [ODBC Drivers](#) in the eServices Integrated Capture Points Guide

In particular:

- Support of 32-bit platforms was discontinued in the 8.1.3 release. Interaction Server requires a 64-bit operating system and a 64-bit version of the ODBC driver.
- Support of the IBM DB2 database was discontinued in the 8.5.2 release.
- Support of the Solaris and IBM AIX platforms was discontinued in the 8.5.3 release.
- Database vendors have released new ODBC drivers with simplified installation processes.

Installing ODBC drivers

Important

- As Interaction Server is a 64-bit application, the ODBC driver must support 64-bit architecture.
- Installation of ODBC drivers might require administrator-level account privileges.
- Interaction Server does not support alternative ODBC drivers and tools from third-party brands, unless they are explicitly listed in this document.

You must ensure that ODBC drivers are installed on each Interaction Server machine in your

environment (primary and backup).


- For Microsoft SQL Server, Genesys recommends the most recent 17.x driver release. See one of the following pages for more information: [Windows](#) or [Linux](#).
- For Oracle, Genesys recommends the most recent 18.x driver release. See one of the following pages for more information: [Windows](#) or [Linux](#).
- For PostgreSQL, Genesys recommends the most recent 10.x driver release. See one of the following pages for more information: [Windows](#) or [Linux](#).

It is recommended to configure the Data Source Name (DSN) for the hosts on which Interaction Server will run (see the [DSN article in Wikipedia](#) for more information). Follow the vendor instructions to install the ODBC driver and configure the DSN. Verify a successful connection to database with the tools that accompany the driver.

Configuring the DSN


You can use the **ODBC Data Source Administrator** in Windows to create driver-specific DSN objects:

1. Open a command prompt.
2. Enter the command `odbcad32` to open the **ODBC Data Source Administrator**.
3. Select the **Drivers** tab to view the ODBC drivers installed in your environment. Note the names of the available drivers.



4. Switch to the tab for DSN creation:


- If Interaction Server is started as a console application or by LCA (Local Control Agent), you must use the tab **User DSN**.
- If Interaction Server is started as a service by the SYSTEM account on Windows, you must use the tab **System DSN**.



5. Select **Add** and follow the vendor instructions to configure the DSN, specific to your database engine and the selected driver.

Important

For Oracle, ensure you check **Enable LOBs** in the **Oracle** tab.



Oracle ODBC Driver Configuration

Data Source Name:

Description:

TNS Service Name:

User ID:

OK Cancel Help Test Connection

Application Oracle Workarounds SQLServer Migration

Fetch Buffer Size:

Enable LOBs: ☒

Enable Statement Caching: ☐

Cache Buffer Size:

Max Token Size:

Translate ORA errors: ☐

Failover Support

Enable Failover: ☒

Retry:

Delay:

Aggregate SQL Type:

Preparing DAP configuration objects

New environment

For a new environment, create a Database Access Point (DAP) object as described in the [Framework Database Connectivity Reference Guide](#) and add the DAP to the connections of your Interaction Server.

To configure the database-oriented [Event Logger](#) for Interaction Server, create a second DAP object as described on the [Deploying Event Logger](#) page.

Existing environment

For an existing environment, use [Genesys Administration Extension \(GAX\)](#) to create copies of the existing DAP objects used by Interaction Server. You can use these copies to switch back to connecting via DB Server while testing.


Updating configuration objects to use ODBC

In the DAP object that defines the connection to the Interaction Server main database:

1. Create or change the option dbprotocol with the value `odbc`.
2. Create or change the option odbc-string to one of the following values:
 - If you have created a DSN object for the main database, enter the value `"DSN={name_of_DSN}"`.
 - Otherwise, enter `"Driver={name_of_driver}"`.

In the sample picture below, the respective values are:

- `DSN={ci-vm410}`
- `Driver={ODBC Driver 17 for SQL Server}`



The steps are similar to set up the DAP object for the Event Logger database:

1. Create or change the option delivery-protocol to the value `odbc`.
2. Create or change the option odbc-string to one of the following values:
 - If you have created a DSN object for the Event Logger database, enter the value

"DSN={name_of_DSN_for_Logger}".

- Otherwise, enter "Driver={name_of_driver}".

If you are using the same location for the main database and the Event Logger database, the values of these options might be identical. However, for performance or other reasons, you might have the Interaction Server main database and the Event Logger database installed in different locations.

Important

Genesys recommends that you do not use different database engine types simultaneously. For example, do not use Oracle for the main database and Microsoft SQL Server for the Event Logger database.

Additional information for Linux

Important

unixODBC driver manager is required to be installed in order to have Interaction Server use ODBC on Linux. For information on how to install unixODBC, refer to **ODBC Connection**.

If Interaction Server is running on Linux, the value for the option `odbc-string` in DAP objects might depend on where the driver's files were installed. For example, if you are not using a DSN, the driver name might be the actual location of the file, such as in the examples below:

- Microsoft SQL Server: `Driver=/opt/microsoft/msodbcsql17/lib64/libmsodbcsql-17.2.so.0.1`
- Oracle: `Driver=/usr/lib/oracle/18.3/client64/lib/libsqora.so.18.1`
- PostgreSQL: `Driver=/home/username/pgodbc/psqlodbc-version/lib/psqlodbcw.so`

Tip

Refer to the **unixODBC User Manual** for instructions on how to configure DSN and test an ODBC connection using the **isql** tool.

Testing the ODBC connection with Interaction Server

Perform the following steps to test the ODBC connection:

1. Configure Interaction Server to collect the log into a text file with debug-level details. See the [Options Reference](#) for more information on available options.
2. Start Interaction Server and let it run to generate some events for the log.
3. Stop Interaction Server.
4. Open the log and review all parts that include the string **odbc** or the names of associated DAP objects. In the case of a successful ODBC connection, the log contains the following messages:

- Connection to main database:

```
Std 27126 New database connection opened (connection ID: 1)
Std 27113 Checking database integrity (connection ID: 1)
```

- Connection to Event Logger database:

```
Std 27126 New database connection opened (connection ID: 100001)
```

Important

- The connection ID number **100001** indicates a connection to the Event Logger database.
- Interaction Server might open more than one connection to the database when necessary and as directed by the values of the option number-of-database-connections. Subsequent connection ID numbers are incremented accordingly.

Troubleshooting a failed connection

See below for quick troubleshooting hints for first-time connections. Make the necessary changes on the database engine side or in the DAP object.

All databases

- On Linux, you might need to have the location of the ODBC driver listed in the environment variable **LD_LIBRARY_PATH**. This also applies to the unixODBC libraries location.

Microsoft SQL Server

- Ensure the instance name is correct.

Oracle

- Ensure the SID or ServiceName values are correct, and check the listener resolution in the file **tnsnames.ora**.
- Ensure the setting of the environment variable **TNS_ADMIN** points to the folder where the file **tnsnames.ora** is located.
- On Linux, the driver might require the following environment variables to be set:
export NLS_NUMERIC_CHARACTERS=""

```
export NLS_LANG=".UTF8"  
export ORACLE_SID=<ORCL_actual_name>
```

PostgreSQL

- Ensure that permissions to connect from a remote host are managed in the configuration file(s) **pg_hba.conf**.