



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

# Genesys Voice Platform

monitor Section

## monitor Section

- optionsofflineresp
- sip.enable\_dns\_cache
- sip.localuser
- sip.logmsg.allowed
- sip.logmsg.maskoption
- sip.mtusize
- sip.preferred\_ipversion
- sip.proxy.optionsinterval
- sip.proxy.release-recordingclient-session-on-fail
- sip.proxy.release-recordingserver-session-on-fail
- sip.proxy.releaseconfonfailure
- sip.proxy.unavailoptionsinterval
- sip.route.default.tcp
- sip.route.default.tcp.ipv6
- sip.route.default.tls
- sip.route.default.tls.ipv6
- sip.route.default.udp
- sip.route.default.udp.ipv6
- sip.tcp.portrange
- sip.tls.portrange
- sip.transport.0
- sip.transport.0.tos
- sip.transport.1
- sip.transport.1.tos
- sip.transport.2
- sip.transport.2.tos
- sip.transport.dnsharouting
- sip.transport.localaddress
- sip.transport.localaddress\_ipv6
- sip.transport.localaddress.srv
- sip.transport.routefailovertime
- sip.transport.routerecoverytime
- sip.transport.setuptimer.tcp
- sip.transport.unavailablewakeupp

### optionsofflineresp

**Default Value:** 503

**Valid Values:**

**Changes Take Effect:** At start/restart

List of semi-colon separated SIP-OPTIONS response codes  $\geq 300$  which can be used to mark a resource offline. If the response code received is not present in the list, then the resource will be considered online. Default is 503 which is the shutdown response code for OPTIONS by MCP

### sip.enable\_dns\_cache

**Default Value:** true

**Valid Values:** true, false

**Changes Take Effect:** At start/restart

Specifies if RM should enable or disable the use of DNS cache. Enabling DNS cache increases RM's

resilience towards network issues between RM and the DNS Servers. If the option is enabled, the target address is retrieved from the DNS cache, if available. If unavailable, a fresh DNS query will be used to retrieve the target address and the result will be cached depending on the DNS query response. If the option is disabled, target address is resolved by a fresh DNS query.

## sip.localuser

**Default Value:** GVP

**Valid Values:**

**Changes Take Effect:** After restart

SIP user presented in OPTIONS requests. The specified text will be presented in the "From:" field of the form sip:user@host[:port]

## sip.logmsg.allowed

**Default Value:** true

**Valid Values:** Choose between: true or false

**Changes Take Effect:** At start/restart

Specifies whether or not logging SIP message is allowed. This option can disable SIP message logging regardless the [log].verbose setting.

## sip.logmsg.maskoption

**Default Value:** 0

**Valid Values:** An integer greater or equal to 0.

**Changes Take Effect:** At start/restart

Specifies the option to restrict SIP message logging. Each bit in the value (starting with LSB) indicates that a specific entity of the SIP message is masked. These bits can be logically OR'ed (or numerically added) and the final value is set. Currently the following bits are supported:

value 1 - indicates all unknown headers (headers other than "Via", "From", "To", "Max-Forwards", "CSeq", "Call-ID", "Contact", "Content-Length", "Content-Type", "Record-Route", "Route", "Refer-To", "Allow-Events", "Subscription-State", "Event", "RSeq", "RAck") will be masked.

value 2 - indicates all user data headers (headers starting with "X-Genesys-" except "X-Genesys-GVP-Session-Data", "X-Genesys-GVP-Session-ID", "X-Genesys-CallUUID") will be masked.

value 4 - indicates all SIP message bodies will be masked.

value 8 - indicates the SIP message bodies with the content type "application/dtmf-relay" or "application/dtmf" will be masked.

value 16 - indicates the values of MSML tag "gvp:param" with the name start with "X-Genesys-" in SIP message bodies will be masked.

For example, to mask all unknown headers and message bodies, set the value to 5 (i.e. 1 + 4). To mask all user data headers and the values of MSML tag "gvp:param" with the name start with "X-Genesys-" in SIP message bodies, set the value to 18 (i.e. 2 + 16). Default value is 0, meaning no masking at all.

## sip.mtusize

**Default Value:** 1500

**Valid Values:**

**Changes Take Effect:** After restart

Defines the Maximum Transmission Unit (MTU) of the network interfaces. If a SIP request size is within 200 bytes of this value, the request will be sent on a congestion controlled transport protocol, such as TCP.

## sip.preferred\_ipversion

**Default Value:** ipv4

**Valid Values:** ipv4, ipv6

**Changes Take Effect:** At start/restart

Preferred IP version to be used in SIP. When multiple IP addresses with different IP versions are resolved from a destination address, the first address from the list with the preferred IP version will be used. However, if there is no sip.transport defined for the preferred version, other version will be used. Valid values are "ipv4" and "ipv6".

## sip.proxy.optionsinterval

**Default Value:** 2000

**Valid Values:**

**Changes Take Effect:** After restart

Specified in milliseconds, this is the interval by which RM sends OPTIONS message to a healthy resource to determine if the resource is alive

## sip.proxy.release-recordingclient-session-on-fail

**Default Value:** true

**Valid Values:**

**Changes Take Effect:** After restart

Can be true or false. If true is specified and the resource that handles the Recording Client session went offline, then all associated Recording Client session calls are released and the new coming calls will be routed to the next available Recording Client resource. If false is specified, new calls that are joining the Recording Client session will receive an error until the Recording Client session is released, when the session timer expires.

## sip.proxy.release-recordingserver-session-on-fail

**Default Value:** true

**Valid Values:**

**Changes Take Effect:** After restart

Can be true or false. If true is specified and the resource that handles the Recording Server session went offline, then all associated Recording Server session calls are released and the new coming calls will be routed to the next available Recording Server resource. If false is specified, new calls that are joining the Recording Server session will receive an error until the Recording Server session is released, when the session timer expires.

## sip.proxy.releaseconfonfailure

**Default Value:** true

**Valid Values:**

**Changes Take Effect:** After restart

Can be true or false. If true is specified and the resource that handles the conference went offline, then all associated conference sessions are released and the new coming calls will be routed to the next available conference resource. If false is specified, new calls that are joining the conference will receive an error until the conference is released, when the session timer expires.

## sip.proxy.unavailoptionsinterval

**Default Value:** 5000

**Valid Values:**

**Changes Take Effect:** After restart

Specified in milliseconds, this is the interval by which RM sends OPTIONS message to a dead resource to determine if the resource has become alive

## sip.route.default.tcp

**Default Value:**

**Valid Values:**

**Changes Take Effect:** At start/restart

Default IPv4 route for TCP. The number denotes the transport defined in sip.transport.x where x is the value of this parameter and will be used when no IPv4 TCP routes are found.

## sip.route.default.tcp.ipv6

**Default Value:**

**Valid Values:**

**Changes Take Effect:** At start/restart

Default IPv6 route for TCP. The number denotes the transport defined in sip.transport.x where x is the value of this parameter and will be used when no IPv6 TCP routes are found. If this parameter is not set, the first IPv6 TCP transport found in sip.transport.x becomes the default.

## sip.route.default.tls

**Default Value:**

**Valid Values:**

**Changes Take Effect:** At start/restart

Default IPv4 route for TLS. The number denotes the transport defined in sip.transport.x where x is the value of this parameter and will be used when no IPv4 TLS routes are found.

## sip.route.default.tls.ipv6

**Default Value:**

**Valid Values:**

**Changes Take Effect:** At start/restart

Default IPv6 route for TLS. The number denotes the transport defined in sip.transport.x where x is the value of this parameter and will be used when no IPv6 TLS routes are found. If this parameter is not set, the first IPv6 TLS transport found in sip.transport.x becomes the default.

## sip.route.default.udp

**Default Value:**

**Valid Values:**

**Changes Take Effect:** At start/restart

Default IPv4 route for UDP. The number denotes the transport defined in sip.transport.x where x is the value of this parameter and will be used when no IPv4 UDP routes are found.

## sip.route.default.udp.ipv6

**Default Value:**

**Valid Values:**

**Changes Take Effect:** At start/restart

Default IPv6 route for UDP. The number denotes the transport defined in sip.transport.x where x is the value of this parameter and will be used when no IPv6 UDP routes are found. If this parameter is not set, the first IPv6 UDP transport found in sip.transport.x becomes the default.

## sip.tcp.portrange

**Default Value:**

**Valid Values:** Possible values are the empty string or low-high, where low and high are integers from 1030 to 65535 inclusive

**Changes Take Effect:** At start/restart

The local TCP port range to be used for SIP transport. If this parameter is not specified, RM will let the OS choose the local port.

## sip.tls.portrange

**Default Value:**

**Valid Values:** Possible values are the empty string or low-high, where low and high are integers from 1030 to 65535 inclusive

**Changes Take Effect:** At start/restart

The local TLS port range to be used for SIP transport. If this parameter is not specified, RM will let the OS choose the local port.

## sip.transport.0

**Default Value:** transport0 udp:any:5064

**Valid Values:**

**Changes Take Effect:** After restart

These parameters define transport layer for SIP stack and the network interfaces that are used to process SIP requests. type:ip:port [parameters]

where transport\_name is any string; type is udp/tcp/tls; ip is the IP address of the network interface that accepts incoming SIP messages; If ip is an IPv6 address, [] must be used. To define a transport to listen to all IPv4 interfaces, use "any" or "any4" for ip. To define a transport to listen to all IPv6 interfaces, use "any6" for ip; port is the port number where SIP stack accepts incoming SIP messages;

[parameters] defines any extra SIP transport parameters.

Example:

cert=[cert path and filename] Applicable to SIPS only and mandatory if using SIPS. The path and the filename of the TLS certificate to be used key=[key path and filename] Applicable to SIPS only and mandatory if using SIPS. The path and the filename of the TLS key to be used. type=[Type of secure transport] Applicable to SIPS only and is optional. The type of secure transport to be used and value

can be TLSv1, SSLv3, SSLv23, TLSv1\_1, TLSv1\_2. Default to TLSv1\_2. Note that SSLv2 is no longer supported. password=[password] Applicable to SIPS only and is optional. The password associated with the certificate and key pair. Required only if key file is password protected. cafile=[CA cert path and filename] Mandatory for TLS mutual authentication. The path and the filename of the certificate to be used for verifying the peer. The same certificate specified in cert=[cert path and filename] parameter can be used as the value here if using only 1 certificate is preferred. verifypeer=true Mandatory for TLS mutual authentication. This parameter turns on the TLS mutual authentication. verifydepth=[max depth for the certificate chain verification] Applicable only to TLS mutual authentication. This parameter sets the maximum depth for the certificate chain verification. For the default Genesys certificate provided, the recommended value is 1. tls-cipher-list=[List of ciphers that are applicable for the socket] Applicable only to TLS socket - both server and client sockets. This parameter allows selecting a list of cipher suites used in TLS. This option is transferred to a third-party library and describes a possible set of cipher suites. Refer to <https://www.openssl.org/docs/man1.0.2/man1/ciphers.html> for Cipher list format. Default is ALL:!EXPORT:!LOW:!aNULL:!eNULL:!SSLv2 crlenabled=true Mandatory for CRL validation. Enabling this parameter will only validate the CRL on the client connection(For Server Certificate). To validation the CRL on server connection(For Client Certificate) the verifypeer should be enabled along with this parameter. crlpaths=[CRL cert filenames with absolute path] Mandatory for CRL validation. The filenames of semi-colon separated certificates for CRL validation. Note: The max path length supported for certificate and key file/path is 259 characters.

## sip.transport.0.tos

**Default Value:** 0

**Valid Values:** Possible values are integers from 0 to 255 inclusive.

**Changes Take Effect:** At start/restart

Specifies the IP Differentiated Services Field (also known as ToS) to set in all outgoing SIP packets over the SIP transport. Note that this configuration does not work for Windows 2008 and above. For Windows 2008 and above, the setting needs to be configured at the OS level through the policy settings. Please refer to the GVP User's Guide.

## sip.transport.1

**Default Value:** transport1 tcp:any:5064

**Valid Values:**

**Changes Take Effect:** After restart

These parameters define transport layer for SIP stack and the network interfaces that are used to process SIP requests. type:ip:port [parameters]

where transport\_name is any string; type is udp/tcp/tls; ip is the IP address of the network interface that accepts incoming SIP messages; If ip is an IPv6 address, [] must be used. To define a transport to listen to all IPv4 interfaces, use "any" or "any4" for ip. To define a transport to listen to all IPv6 interfaces, use "any6" for ip; port is the port number where SIP stack accepts incoming SIP messages;

[parameters] defines any extra SIP transport parameters.

Example:



---

cert=[cert path and filename] Applicable to SIPS only and mandatory if using SIPS. The path and the filename of the TLS certificate to be used key=[key path and filename] Applicable to SIPS only and mandatory if using SIPS. The path and the filename of the TLS key to be used. type=[Type of secure transport] Applicable to SIPS only and is optional. The type of secure transport to be used and value can be TLSv1, SSLv3, SSLv23, TLSv1\_1, TLSv1\_2. Default to TLSv1\_2. Note that SSLv2 is no longer supported. password=[password] Applicable to SIPS only and is optional. The password associated with the certificate and key pair. Required only if key file is password protected. cafile=[CA cert path and filename] Mandatory for TLS mutual authentication. The path and the filename of the certificate to be used for verifying the peer. The same certificate specified in cert=[cert path and filename] parameter can be used as the value here if using only 1 certificate is preferred. verifypeer=true Mandatory for TLS mutual authentication. This parameter turns on the TLS mutual authentication. verifydepth=[max depth for the certificate chain verification] Applicable only to TLS mutual authentication. This parameter sets the maximum depth for the certificate chain verification. For the default Genesys certificate provided, the recommended value is 1. tls-cipher-list=[List of ciphers that are applicable for the socket] Applicable only to TLS socket - both server and client sockets. This parameter allows selecting a list of cipher suites used in TLS. This option is transferred to a third-party library and describes a possible set of cipher suites. Refer to <https://www.openssl.org/docs/man1.0.2/man1/ciphers.html> for Cipher list format. Default is ALL:!EXPORT:!LOW:!aNULL:!eNULL:!SSLv2 crlenabled=true Mandatory for CRL validation. Enabling this parameter will only validate the CRL on the client connection(For Server Certificate). To validation the CRL on server connection(For Client Certificate) the verifypeer should be enabled along with this parameter. crlpaths=[CRL cert filenames with absolute path] Mandatory for CRL validation. The filenames of semi-colon separated certificates for CRL validation. Note: The max path length supported for certificate and key file/path is 259 characters.

## sip.transport.1.tos

**Default Value:** 0

**Valid Values:** Possible values are integers from 0 to 255 inclusive.

**Changes Take Effect:** At start/restart

Specifies the IP Differentiated Services Field (also known as ToS) to set in all outgoing SIP packets over the SIP transport. Note that this configuration does not work for Windows 2008 and above. For Windows 2008 and above, the setting needs to be configured at the OS level through the policy settings. Please refer to the GVP User's Guide.

## sip.transport.2

**Default Value:** transport2 tls:any:5065 cert=\$InstallationRoot\$/config/x509\_certificate.pem

key=\$InstallationRoot\$/config/x509\_private\_key.pem

**Valid Values:**

**Changes Take Effect:** After restart

These parameters define transport layer for SIP stack and the network interfaces that are used to process SIP requests. type:ip:port [parameters]

where transport\_name is any string; type is udp/tcp/tls; ip is the IP address of the network interface that accepts incoming SIP messages; If ip is an IPv6 address, [] must be used. To define a transport to listen to all IPv4 interfaces, use "any" or "any4" for ip. To define a transport to listen to all IPv6

interfaces, use "any6" for ip; port is the port number where SIP stack accepts incoming SIP messages; [parameters] defines any extra SIP transport parameters.

Example:

cert=[cert path and filename] Applicable to SIPS only and mandatory if using SIPS. The path and the filename of the TLS certificate to be used key=[key path and filename] Applicable to SIPS only and mandatory if using SIPS. The path and the filename of the TLS key to be used. type=[Type of secure transport] Applicable to SIPS only and is optional. The type of secure transport to be used and value can be TLSv1, SSLv3, SSLv23, TLSv1\_1, TLSv1\_2. Default to TLSv1\_2. Note that SSLv2 is no longer supported. password=[password] Applicable to SIPS only and is optional. The password associated with the certificate and key pair. Required only if key file is password protected. cafile=[CA cert path and filename] Mandatory for TLS mutual authentication. The path and the filename of the certificate to be used for verifying the peer. The same certificate specified in cert=[cert path and filename] parameter can be used as the value here if using only 1 certificate is preferred. verifypeer=true Mandatory for TLS mutual authentication. This parameter turns on the TLS mutual authentication. verifydepth=[max depth for the certificate chain verification] Applicable only to TLS mutual authentication. This parameter sets the maximum depth for the certificate chain verification. For the default Genesys certificate provided, the recommended value is 1. tls-cipher-list=[List of ciphers that are applicable for the socket] Applicable only to TLS socket - both server and client sockets. This parameter allows selecting a list of cipher suites used in TLS. This option is transferred to a third-party library and describes a possible set of cipher suites. Refer to <https://www.openssl.org/docs/man1.0.2/man1/ciphers.html> for Cipher list format. Default is ALL:!EXPORT:!LOW:!aNULL:!eNULL:!SSLv2 crlenabled=true Mandatory for CRL validation. Enabling this parameter will only validate the CRL on the client connection(For Server Certificate). To validation the CRL on server connection(For Client Certificate) the verifypeer should be enabled along with this parameter. crlpaths=[CRL cert filenames with absolute path] Mandatory for CRL validation. The filenames of semi-colon separated certificates for CRL validation. Note: The max path length supported for certificate and key file/path is 259 characters.

## sip.transport.2.tos

**Default Value:** 0

**Valid Values:** Possible values are integers from 0 to 255 inclusive.

**Changes Take Effect:** At start/restart

Specifies the IP Differentiaed Services Field (also known as ToS) to set in all outgoing SIP packets over the SIP transport. Note that this configuration does not work for Windows 2008 and above. For Windows 2008 and above, the setting needs to be configured at the OS level through the policy settings. Please refer to the GVP User's Guide.

## sip.transport.dnsharouting

**Default Value:** false

**Valid Values:** true, false

**Changes Take Effect:** At start/restart

Specifies whether the DNS HA routing based on RFC3263 should be turned on. If turned off, alternate records returned from the DNS query will not be tried. Otherwise, alternate records returned from the

DNS query will be tried based on RFC3263.

## sip.transport.localaddress

**Default Value:**

**Valid Values:**

**Changes Take Effect:** At start/restart

If specified, the sent-by field of the Via header and the hostport part of the Contact header in the outgoing SIP message will be set to this value if a IPv4 transport is used. The value must be a hostname or domain name. If left empty the outgoing transport's actual IP and port will be used for the Via header, and the Contact header. Note that if the domain name used in the SRV record query is specified, sip.transport.localaddress.srv must be set to true to prevent the port part being automatically generated by the SIP stack.

## sip.transport.localaddress\_ipv6

**Default Value:**

**Valid Values:**

**Changes Take Effect:** At start/restart

If specified, the sent-by field of the Via header and the hostport part of the Contact header in the outgoing SIP message will be set to this value if a IPv6 transport is used. The value must be a hostname or domain name. If left empty the outgoing transport's actual IP and port will be used for the Via header, and the Contact header. Note that if the domain name used in the SRV record query is specified, sip.transport.localaddress.srv must be set to true to prevent the port part being automatically generated by the SIP stack.

## sip.transport.localaddress.srv

**Default Value:** false

**Valid Values:** true, false

**Changes Take Effect:** At start/restart

Specifies whether the sip.transport.localaddress contains an SRV domain name. If set to true, port part will not be automatically generated by the SIP stack. Otherwise, the outgoing transport's port will be used together with the hostname specified by the sip.transport.localaddress.

## sip.transport.routefailovertime

**Default Value:** 5

**Valid Values:**

**Changes Take Effect:** At start/restart

Specifies the failover time in seconds for SIP static routing and DNS HA routing. If a SIP request has not received a response within the failover time, and SIP static routing or DNS HA routing is enabled, the SIP request will be retransmitted to an alternate route.

## sip.transport.routerecoverytime

**Default Value:** 30

**Valid Values:**

**Changes Take Effect:** At start/restart

Specifies the recovery time in seconds for SIP static routing and DNS HA routing. When SIP static routing or DNS HA routing is enabled and the route is marked as unavailable due to error or SIP response timeout, the route will be marked as available again after the recovery time.

## sip.transport.setuptimer.tcp

**Default Value:** 30000

**Valid Values:** Possible values are integers from 1000 to 32000 inclusive.

**Changes Take Effect:** At start/restart

Specifies the maximum wait time in milliseconds for establishing a TCP or TLS connection before marking the resource unavailable.

## sip.transport.unavailablewakeup

**Default Value:** true

**Valid Values:** true, false

**Changes Take Effect:** At start/restart

Specifies whether unavailable route destinations can be made active if needed before the route recover timer expires. The unavailable destinations would be made active only when all destinations corresponding to a static route group or DNS SRV domain are unavailable. This parameter is applicable when SIP stack is running under HA mode (Static route list or DNS SRV routing).