



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Genesys Voice Platform

provision Section

4/8/2025

provision Section

- `vrn.client.ConnectPerSetup`
- `vrn.client.DisablePing`
- `vrn.client.NoSpeechLanguageHeader`
- `vrn.client.resource.name`
- `vrn.client.resource.type`
- `vrn.client.resource.uri`
- `vrn.client.SendLoggingTag`
- `vrn.client.SpeechMarkerEncoding`
- `vrn.client.TransportProtocol`
- `vrn.client.TTSInsertVoiceTag`
- `vrn.proxy.ping_interval`

vrn.client.ConnectPerSetup

Default Value: false

Valid Values:

Changes Take Effect: At start/restart

When this option is set to true the SRM Client will create a new connection to the ASR or TTS server per MRCP session setup.

vrn.client.DisablePing

Default Value: false

Valid Values:

Changes Take Effect: At start/restart

When this option is set to true the MRCPv1 Client will not ping the MRCPv1 server.

vrn.client.NoSpeechLanguageHeader

Default Value: false

Valid Values:

Changes Take Effect: At start/restart

When this parameter is set to true, the SRM Client will not send the Speech-Language header in MRCP SET-PARAMS and SPEAK requests in a TTS session. Without the Speech-Language header, some MRCP TTS servers is able to use its default language when the application specified language is absent.

vrn.client.resource.name

Default Value:

Valid Values:

Changes Take Effect: At start/restart

This parameter specifies the name of resource name. Some common names are SPEECHWORKS, REALSPEAK

vrn.client.resource.type

Default Value: TTS

Valid Values:

Changes Take Effect: At start/restart

This parameter specifies the speech resource type.

vrn.client.resource.uri

Default Value:

Valid Values:

Changes Take Effect: At start/restart

This parameter specifies the URI to the speech resource, e.g. rtsp://<MRCP server IP>:<port>/media/speechsynthesizer. Please consult your MRCP vendor documentation for appropriate setting.

vrn.client.SendLoggingTag

Default Value: true

Valid Values:

Changes Take Effect: At start/restart

When this option is set to true the SRM Client will set the logging-tag parameter in the first SET-PARAMS method to the unique Call ID of the call.

vrn.client.SpeechMarkerEncoding

Default Value: UTF-8

Valid Values:

Changes Take Effect: At start/restart

If a TTS MRCP server does not have the content-encoding header to specify the Speech Marker name

encoding in a SPEECH-MARKER event, the SRM client will use the value specified by this parameter as the encoding of the Speech Marker name.

vrn.client.TransportProtocol

Default Value: MRCPv1

Valid Values:

Changes Take Effect: At start/restart

This parameter specifies the MRCP protocol used by the Speech Resource.

vrn.client.TTSInsertVoiceTag

Default Value: false

Valid Values:

Changes Take Effect: At start/restart

When this option is set to true, the SRM Client will use the voice name defined in the TTSENGINE property to tell the TTS engine what voice to use.

vrn.proxy.ping_interval

Default Value: 30000

Valid Values:

Changes Take Effect: Immediately

This parameter specifies the ping interval in milliseconds for the MRCP Proxy to ping the speech resource. This parameter is only used by the MRCP proxy.