



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

# User's Guide

## Installing Context Services

# Installing Context Services

This page details how you can install, then enable the Context Services APIs.

If your application needs the Customer Profile API due to backward compatibility issues, refer the [migration page of this guide](#).

## Contents

- [1 Installing Context Services](#)
  - [1.1 Installing the Genesys Mobile Services](#)
  - [1.2 Enabling Context Services](#)
  - [1.3 Accessing Context Services](#)
  - [1.4 Checking that your Installation is Successful](#)

# Installing the Genesys Mobile Services

Context Services uses the GMS platform to store data and implement additional features. In order to install the GMS/CS component, you must deploy GMS first. See the [GMS Deployment Guide](#) for details.

The Context Services installation CD contains a single installation package for both GMS and CS components. Follow GMS instructions prior to your installation. In particular, you must create a GMS application that you will use to enable and configure the Context Services.

Run the installation package of your GMS installation CD:


1. Navigate to the installation directory `\windows\b1\ip`
2. Double-click `install.exe` which is located in this directory.
3. Follow instructions and enter the destination folder for the GMS installation.

### Important

If you already installed a version of GMS older than 8.5.006.07, you must upgrade to GMS version 8.5.006.07 or higher.

## Licensing

The GMS installation includes all Context Services materials, including licensing. The installation wizard displays the following information for licensing:



The licensing materials include Context Services. If you select the Use License option, your users will have access to Genesys Mobile Services Functions, including Context Services.

## Enabling Context Services

### Procedure:


**Purpose:** To configure the cview variable which enables the Context Services.

#### Steps

1. Start Genesys Administrator the Configuration Manager and navigate to **PROVISIONING > Environment > Applications**.
2. Edit your GMS application.
3. Select the Options tab, and click **New** to create a new option.
  - Enter cview for the **Section**.

- Enter enabled for the **Name**.
- Enter true for the **Value**.

4. Click **OK**.



## Accessing Context Services

Once Context Services is installed, enabled, and started, the services are available at the `<GMS_HOST_BASE_URL>/genesys/1/cs` base URL of your GMS host. Note that the `<GMS_HOST_BASE_URL>` must map the `server/external_url_base` option set in your application.

## Checking that your Installation is Successful

The Genesys Mobile Services platform sees the Context Services as custom items and if your installation is successful, you can see Context Services in the home page of the Service Management User Interface.

- You can get detailed information about the Service Management User Interface [here](#).
- You can also use the [Context Services interface](#) to manage your services.