



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Knowledge Center

Knowledge Center Content Management System (CMS)

12/19/2025

Knowledge Center Content Management System (CMS)

Options for this component are contained in the following configuration sections:

- [gks-security](#)
- [log](#)
- [log-extended](#)

Tip

In the summary table(s) below, type in the Search box to quickly find options, configuration sections, or other values, and/or click a column name to sort the table. Click an option name to link to a full description of the option. Be aware that the default and valid values are the values in effect with the latest release of the software and may have changed since the release you have; refer to the full description of the option to see information for earlier releases.

Power users: [Download a CSV file](#) containing default and valid values and descriptions.

The following options are configured at the application level (in other words, on the application object).

Section	Option	Default	Changes Take Effect
gks-security	enable-ssl	false	At start/restart
gks-security	truststore-password		At start/restart
gks-security	truststore-path	./trustStore.jks	At start/restart
log	affectedLoggers		immediately
log	all	stdout	Immediately
log	compressMethod		Immediately
log	debug	stdout	Immediately
log	expire	10	Immediately
log	message-format	custom	Immediately
log	outputPattern	%d{dd.MM.yyyy HH:mm:ss} %-5.5p %-45.80t %-30.1000c{1} %m %ex%n	Immediately
log	segment	100 MB	Immediately
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
log	standard	stdout	Immediately
log	timeConvert	local	Immediately
log	timeFormat	time	Immediately
log	time_convert	local	immediately
log	time_format	time	immediately
log	trace	stdout	Immediately
log	verbose	standard	Immediately
log-extended	logger-config	config: level=info	immediately
log-extended	logger-gks	gks: level=info	immediately
log-extended	logger-http	http: level=info	immediately
log-extended	logger-rest	timing: level=trace	immediately
log-extended	logger-sql	p6spy: level=off	immediately
log-extended	logger-timing	timing: level=trace	immediately
Section	Option	Default	Changes Take Effect