Microsoft Skype for Business Deployment Guide

Error Messages

4/17/2025

Error Messages

This table presents the complete set of error messages T-Server distributes in EventError, which T-Server generates when it cannot execute a request because of an error condition.

Code	Symbolic Name	Description
40	TERR_NOMORE_LICENSE	No more licenses are available.
41	TERR_NOT_REGISTERED	Client has not registered for the DN.
42	TERR_RESOURCE_SEIZED	Resource is already seized
43	TERR_IN_SAME_STATE	Object is already in requested state.
50	TERR_UNKNOWN_ERROR	Unknown error code. Request cannot be processed.
51	TERR_UNSUP_OPER	Operation is not supported.
52	TERR_INTERNAL	Internal error.
53	TERR_INVALID_ATTR	Attribute in request operation is invalid.
55	TERR_PROTO_VERS	Incorrect protocol version.
56	TERR_INV_CONNID	Connection ID in request is invalid.
57	TERR_TIMEOUT	Switch or T-Server did not respond in time.
58	TERR_OUT_OF_SERVICE	Device is out of service.
59	TERR_NOT_CONFIGURED	DN is not configured in the Configuration Database.
61	TERR_INV_CALL_DN	DN in request is invalid.
71	TERR_INV_CALD_DN	Invalid called DN.
93	TERR_DEST_INV_STATE	Destination Invalid State.
111	TERR_TOO_MANY_REQ	Too many outstanding requests.
123	TERR_DN_NOT_EXIST	DN for association does not exist.
177	TERR_TARG_DN_INV	Target DN Invalid.
223	TERR_BAD_PARAM	Bad parameter is passed to function.
226	TERR_OUT_OF_MEM	Out of memory (local).
236	Timeout performing operation	Request failed as no response from Connector (hence from SfB) for requested service received during timeout.
237	Call has disconnected	Request failed due to the main call being disconnected.

Code	Symbolic Name	Description
291	Other telephony operation in progress	Request failed because there is still pending request for the same call/device/etc in progress.
415	TERR_INV_DEST_DN	The destination DN in the request is invalid.
470	TERR_PARTY_NOT_ON_CALL	Party in request is not involved in a call.
481	TERR_NOT_SIGNED_AGENT	The destination agent is not signed in.
496	TERR_INV_CALL_STATE	Party in request is in the call state.
563	TERR_NO_CALL	No call.
565	TERR_INVALID_STATE	Invalid State.
1140	TERR_CSTA_OPER_REQ_INCOMPAT	Request incompatible with object.
1703	TERR_SOFT_AGENT_WRONG_ID	Agent has a wrong ID.
1706	TERR_SOFT_AGENT_ALREADY_LOGGED_IN	Agent has already logged in.
1707	TERR_SOFT_AGENT_NOT_LOGGED_IN	Agent has not logged in.