

GENESYS

This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Callback User's Guide

Enable Callback UI for Administrators

Enable Callback UI for Administrators

The Callback UI enables you to create services based on the provided Scenarios and is embedded in the Service Management UI of Genesys Mobile Environment. To access the Callback UI, make sure that GMS is started and that your user owns Supervisor or Administrator permissions.

Setting permissions to Callback Administrators

Configuration Man	ager					
Access Groups Agent Groups Capacity Rules Persons	Home > F	Persons > Persons	More G Show	Quick Filter Direct	Persons (Person Folder)	
Roles		Username 🎍	First Name 🛛 🗟	Last Name 🗧	Agent	7
		🚨 admin	admin			
Accounts		archiveUser_tenant1				
		becadmin	becadmin	becadmin		
	(\cdot)	1 bobdema	Bob	Demo	~	
		im (2)	cim			
			cloudadmin			
		Cloudsupervisor	Cloudsupervis		×	
		L cobrowse	cobrowse			
		@e	Carole	Spencer	1	

Open GAX and select the **Configuration Manager** section. In the **Accounts** menu, select **Persons** to get the list of configured users.

Edit the person who will be logging into the Service Management UI. You are going to give this user the permissions to read/write data into Callback related configuration objects (for example, GMS Application, Business Attributes, Transaction Lists for Resources/Patterns, and so on).

General (DBID: 8084)	Ontione			O Quick File		Delata	
(DDID: 0904)	options			Q QUICK FIII	ter	Delete	Add yr Mol
Member Of		Key		¢ ♥	Value	(2)	\$
Ranks	No ite	ms					
Skills							
Agent Logins						K	
Options)		New	1		×	
Permissions			Section	on *		e	
Dependencies			gms		>		
Accessible Objects	4		Key*				
			roles	3			
	Canc	el	Value	•		ply	Save
			Adm	inistrator			

In the **Options** tab, click **Add** to set the gms/roles option:

- Enter gms for **Section**,
- Enter roles for **Key**,
- Enter one of the following values:
 - Supervisor: Role used to monitor and configure Callbacks only.
 - Administrator: Role used to administer the creation of Callback Services. This role provides access to all panels and includes the **Supervisor** role.
 - CallbackReadOnly: Role used to provide read-only access. The user can see the Callback panel without Create, Update, or Delete capabilities. This role was introduced in 8.5.226.03.