

# **GENESYS**

This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

User's Guide

**Configure UCS Application** 

## Configure UCS Application

**Purpose:** To configure a UCS Application object.

### Contents

- 1 Configure UCS Application
  - 1.1 Configure UCS Application for Context Services
  - 1.2 Next Steps

### Configure UCS Application for Context Services

Senesys		Genes	sys Adm	ninistrato	or	Tenant: Environment	9	New Window   Log out	t   💮 🕶   🔞	•
MONITORING	P <u>R</u> OVISIONING	DEP <u>L</u> OYMENT	<u>OPERATIONS</u>							
PROVISIONING	> Environment >	Applications > (	ContactServer							
Navigation	~	ContactS	erver - Started	- Primary - \App	lications\					
🕞 Search	+			Save 🚽 Save &	New 🗟 Reload 📑 Uni	install 📄 Start 🔲 Stop 🗟	Graceful Stop	2		
🕞 Environment 📃		Port Info	Continueration Ontions Dermissions Denendencies Alarms				Logs			
Alarm Conditions		General	General Advanced Network Security					General Server Info	Network Securi	ity
Scripts								[Unknown Trace M		~
Application Templates		* ID:		cview				Trace Is Turned Off		
Applications		Port:	Port: Connection Protocol:		9080					
- Hosts		Connec			http 🗸					
Solutions		HA sync:		🗖 True						
Time Zones		Select Listening Mode:		Unsecured 🗸						
Business Units/Sites		Descrip	Description:							
Tenants		,						×	9	
Table Acces	e Dointe	* Listening								
💫 Switching	+	411				OK	Cancel			
Routing/eServ	rices +			cview	9080					
😝 Desktop 🛛 🕂		* Working Directory: * Command Line:		default 4400						
Accounts +				C:\Program Files (x86)\GCTT\eServices 8.1.0\Universal Contact Server\ContactServer						
Voice Platform +				ContactServerDriver.exe						
Outbound Contact +										~
Ready									3/25/20	)16

Prerequisites: It is preferable to set up the database and configure a DAP before creating the Application object.

- 1. On the **General** tab, enter a name.
- 2. On the Server Info tab, enter a host name and add a standard cview port with its protocol set
- 3. On the Start Info tab, enter an arbitrary character. The real values will be entered during insta
- 4. On the **Connections** tab, add connections to the UCS DAP, Message Server, and Stat Server.
- 5. On the **Options** tab, in the cview section:
  - 1. Set enabled to true.
  - 2. Set tenant-id to the identifier of the tenant with which UCS will be associated.
  - Set other configuration options as needed. All options are described on the Configuration C page.

#### Important

The underscore character ( \_) is not supported for host names that UCS connects to. Having this character in a host name can result in unstable behavior, such as inability to connect to the target host. Note that RFC 1123, section 2.1 "Host Names and Numbers" limits host names to letters, digits, and hyphen. If a host that UCS connects to contains underscore in its name, Genesys recommends that you create an alias and change the host name in the Configuration Layer.

#### Next Steps

- 1. Optionally, configure UCS to use TLS.
- 2. Optionally, configure role privileges for UCS.
- 3. Install UCS. Installing UCS is a simple matter of launching the installation entering Configuration Server login information.