



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

## Composer Help

TLib Block

# TLib Block

## Contents

- **1 TLib Block**
  - 1.1 Name Property
  - 1.2 Block Notes Property
  - 1.3 Exceptions Property
  - 1.4 Condition Property
  - 1.5 Logging Details Property
  - 1.6 Log Level Property
  - 1.7 Result Property
  - 1.8 Application Property
  - 1.9 Content Property
  - 1.10 URL Property
  - 1.11 Enable Status Property

Use this block in workflows and sub-workflows that will use `<session:fetch> method="tlib"`. The block exposes properties to form a TLib request to set agent status not ready equivalent to `TAgentSetNotReady`. It also sets `srcexpr` and `<content>` element to make it possible to form generic TLib requests. The TLib block has the following properties:

### Name Property

Find this property's details under [Common Properties for Workflow Blocks](#).

### Block Notes Property

Find this property's details under [Common Properties for Workflow Blocks](#).

### Exceptions Property

Find this property's details under [Common Properties for Workflow Blocks](#).

### Condition Property

Find this property's details under [Common Properties for Workflow Blocks](#).

### Logging Details Property

Find this property's details under [Common Properties for Workflow Blocks](#).

### Log Level Property

Find this property's details under [Common Properties for Workflow Blocks](#).

### Result Property

Response returned from the TLib function. You may use this property to assign the collected data to a user-defined **variable** for further processing.

1. Select the Output Result row in the block's property table.
2. In the Value field, click the down arrow and select a variable.

## Application Property

The T-Server application object in Configuration Server that represents the third party server to be contacted. You can select Configuration Server, enter a literal or enter a value.

## Content Property

Use this property to specify input parameters to be passed to the specified TLib function. You can enter as literals and enter property names and values or select a variable.

## URL Property

Select the variable that contains the URI for the TLib function that is to be used.

## Enable Status Property

Find this property's details under [Common Properties for Workflow Blocks](#).