



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Genesys Rules System Deployment Guide

Configuring the Business Structure

5/7/2025

Configuring the Business Structure

Contents

- **1 Configuring the Business Structure**
 - 1.1 Sample Business Structure in Genesys Administrator
 - 1.2 Sample Business Structure in Configuration Manager
 - 1.3 Sample Business Structure in the Genesys Rules Authoring Tool


Your Tenant's business structure is created under Resources for single-tenant Configuration Server, or under a Tenant for a multi-tenant Configuration Server.

Navigate to the Resources folder for a single-tenant Configuration Server, or to the specific Tenant for a multi-tenant Configuration Server, and open the Business Units/Sites (in Genesys Administrator) or Configuration Units (in Configuration Manager) folder. Create a new top-level folder named Business Structure. This folder must be named Business Structure.

Within the Business Structure folder, click either New Unit or New Site to create at least one more Business Unit or Site (it does not matter whether you create a site or a unit). This new site/unit will represent the Solution. Within the new folder (the Solution), additional levels of hierarchy can be created as needed, using either Business Units or Sites. The levels of hierarchy beneath the Solution level will represent the business context.

Multiple Solutions can be created by creating additional Business Units or Sites directly beneath the Business Structure folder.

Sample Business Structure in Genesys Administrator




The screenshot shows the Genesys Administrator interface. The top navigation bar includes tabs for MONITORING, PROVISIONING, DEPLOYMENT, and OPERATIONS. The PROVISIONING tab is active, and the breadcrumb path is PROVISIONING > Environment > Business Units/Sites. The left sidebar shows a navigation tree with 'Business Units/Sites' selected. The main pane displays a table of Business Units under the 'ACME Solution' folder.

Name	Type	State
Accounts Payable	Business Unit	Enabled
Order Processing	Business Unit	Enabled


Sample Business Structure in Genesys Administrator

Sample Business Structure in Configuration Manager




Sample Business Structure in Configuration Manager.

Sample Business Structure in the Genesys Rules Authoring Tool



Sample Business Structure in GRAT

Read permission to the Business Structure folder must be provided to the users and/or access groups that you want to use the Rules Authoring Tool. Normally this will be propagated automatically, if the user or access group has permission to the Tenant object. If you do not want a user or access group to have permission to see all of the nodes of the business structure, you can control this by not giving that user or the access group(s) of that use read permission to those folders. The figure below shows that all members of the Users access group have Read permissions to the Business Structure folder.



Business Structure Permissions.