



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Altocloud

Pacing Server Cluster

12/14/2025

Pacing Server Cluster

Options for this component are contained in the following configuration sections:

- [forward-proxy](#)
- [log](#)
- [metrics](#)
- [pacing](#)
- [pacingEndpoint](#)

Tip

In the summary table(s) below, type in the Search box to quickly find options, configuration sections, or other values, and/or click a column name to sort the table. Click an option name to link to a full description of the option. Be aware that the default and valid values are the values in effect with the latest release of the software and may have changed since the release you have; refer to the full description of the option to see information for earlier releases.

Power users: [Download a CSV file](#) containing default and valid values and descriptions.

The following options are configured at the application level (in other words, on the application object).

Section	Option	Default	Changes Take Effect
forward-proxy	host		After service restart
forward-proxy	password		After service restart
forward-proxy	port		After service restart
forward-proxy	user		After service restart
log	all	stdout	Immediately
log	compressMethod		Immediately
log	debug	stdout	Immediately
log	expire	10	Immediately
log	messageFormat	custom	Immediately
log	outputPattern	%d{HH:mm:ss,SSS}{UTC} [%5p] %-30c{1} - %m %ex%n	Immediately
log	segment	100 MB	Immediately
log	standard	stdout	Immediately
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
log	timeConvert	utc	Immediately
log	timeFormat	time	Immediately
log	trace	stdout	Immediately
log	verbose	all	Immediately
metrics	GcFrequency.threshold	24	Immediately
metrics	GcLatency.threshold	1000	Immediately
metrics	HeapMemoryUsage.threshold	0.8	Immediately
metrics	reporter.console.enabled	false	Immediately
metrics	reporter.console.logFrequency	30min	Immediately
metrics	reporter.jmx.enabled	true	Immediately
metrics	reporter.log.enabled	false	Immediately
metrics	reporter.log.logFrequency	30min	Immediately
metrics	reporter.messageServer.enabled	true	Immediately
metrics	reporter.messageServer.logFrequency	30min	Immediately
pacing	optimizationGoal	3	After server restart
pacingEndpoint	authClientId	None	After server restart
pacingEndpoint	authEndpoint	None	After server restart
pacingEndpoint	password	None	After server restart
pacingEndpoint	targetEndpoint	None	After server restart
Section	Option	Default	Changes Take Effect