



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

## Genesys Engage Digital (eServices)

Interaction Server DAP

4/21/2025

# Interaction Server DAP

These options are configured on the main Interaction Server DAP.

## settings Section

- [blob-chunk-size](#)
- [connection-string](#)
- [connections](#)
- [dbprotocol](#)
- [odbc-string](#)
- [queue-size](#)
- [reconnection-pause](#)

## blob-chunk-size

**Default Value:** 1024

**Valid Values:** 1024-65535

**Changes Take Effect:** After restart of Interaction Server

**Introduced:** 8.5.100.18

Specifies, in bytes, the amount of data to be read from a BLOB in each iteration.

## connection-string

**Default Value:** No default value

**Valid Values:** Any valid ODBC connection string

**Changes Take Effect:** After restart of Interaction Server

**Introduced:** 8.5.100.18

Configuring a connection string is described on the [ODBC Connection page](#) of the eServices Deployment Guide.

## connections

**Default Value:** 5

**Valid Values:** 1-50

**Changes Take Effect:** After restart of Interaction Server

**Introduced:** 8.5.100.18

Specifies the number of concurrent connections to the database.

## dbprotocol

**Default Value:** odbc

**Valid Values:** odbc

**Changes Take Effect:** After restart of Interaction Server

**Introduced:** 8.5.100.18

To enable an ODBC connection, this option must be present, with its value set to odbc. This option has no other use.

## odbc-string

**Default Value:** No default value

**Valid Values:** Any valid ODBC connection string

**Changes Take Effect:** After restart of Interaction Server

**Introduced:** 8.5.100.18

Configuring a connection string is described on the [ODBC Connection page](#) of the eServices Deployment Guide. Consult the description of the connection-string option.

## queue-size

**Default Value:** 20000

**Valid Values:** 50-65535

**Changes Take Effect:** Immediately

**Introduced:** 8.5.100.18

Specifies the maximum number of requests that can be stored in the queue of requests to the database.

## reconnection-pause

**Default Value:** 5000

**Valid Values:** 100-300000

**Changes Take Effect:** Immediately

**Introduced:** 8.5.100.18

Specifies, in milliseconds, the time between repeated attempts to connect to the database, test database integrity, initialize database values, or reconnect to the database when a connection is lost.