



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Genesys Engage Digital (eServices)

Genesys Driver for SMS and MMS

5/2/2025

Genesys Driver for SMS and MMS

Options for this component are contained in the following configuration sections:

- channel-any_name_for_mms_mm7
- channel-any_name_for_sms
- settings #To be merged with the settings section of DMS#

Tip

In the summary table(s) below, type in the Search box to quickly find options, configuration sections, or other values, and/or click a column name to sort the table. Click an option name to link to a full description of the option. Be aware that the default and valid values are the values in effect with the latest release of the software and may have changed since the release you have; refer to the full description of the option to see information for earlier releases.

Power users: [Download a CSV file](#) containing default and valid values and descriptions.

The following options are configured at the application level (in other words, on the application object).

Section	Option	Default	Changes Take Effect
channel-any_name_for_mms_mm7	driver-classname	com.genesyslab.mcr.smsmms.jsms_mm7.MM7	After restart
channel-any_name_for_mms_mm7	inbound-route	tenant_dbid:endpoint_name_for_mms	After MMS
channel-any_name_for_mms_mm7	reconnection-timeout	180	After restart
channel-any_name_for_mms_mm7	x-debug-mode	false	After restart
channel-any_name_for_mms_mm7	x-jsms-config-file	./media-channel-drivers/channel-smsmms/jsms-mm7.conf	After restart
channel-any_name_for_sms	default-reply-address	No default value	After restart
channel-any_name_for_sms	driver-classname	com.genesyslab.mcr.smsmms.opensmpp.Smpp	After restart
channel-any_name_for_sms	inbound-route	No default value	After restart
channel-	password	No default value	After restart
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
any_name_for_sms			
channel-any_name_for_sms	reconnection-timeout	180	After restart
channel-any_name_for_sms	session-by-address	No default value	After restart
channel-any_name_for_sms	session-by-text	No default value	After restart
channel-any_name_for_sms	x-debug-mode	false	After restart
channel-any_name_for_sms	x-smpp-address-range	No default value	After restart
channel-any_name_for_sms	x-smpp-bind-mode	auto	After restart
channel-any_name_for_sms	x-smpp-comms-timeout	60	After restart
channel-any_name_for_sms	x-smpp-delivery-extraopt	No default value	After restart
channel-any_name_for_sms	x-smpp-delivery-report	noreports	After restart
channel-any_name_for_sms	x-smpp-dest-addr-npi	1	After restart
channel-any_name_for_sms	x-smpp-dest-addr-ton	1	After restart
channel-any_name_for_sms	x-smpp-empty-message	No default value	After restart
channel-any_name_for_sms	x-smpp-enquire-link-timeout	60	After restart
channel-any_name_for_sms	x-smpp-extraopt	No default value	After restart
channel-any_name_for_sms	x-smpp-host	No default value	After restart
channel-any_name_for_sms	x-smpp-inbound-enc-default	301	After restart
channel-any_name_for_sms	x-smpp-outbound-enc-default	301	After restart
channel-any_name_for_sms	x-smpp-port	No default value	After restart
channel-any_name_for_sms	x-smpp-receive-timeout	60	After restart
channel-any_name_for_sms	x-smpp-response-max-waiting-time	30000	After restart
channel-any_name_for_sms	x-smpp-sar-max-segments	255	After restart
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
channel-any_name_for_sms	x-smpp-sar-prompt-responses	false	After restart
channel-any_name_for_sms	x-smpp-service-type	No default value	After restart
channel-any_name_for_sms	x-smpp-src-addr-npi	1	After restart
channel-any_name_for_sms	x-smpp-src-addr-ton	1	After restart
channel-any_name_for_sms	x-smpp-submit-max-rate	10	After restart
channel-any_name_for_sms	x-smpp-submit-window-size	10	After restart
channel-any_name_for_sms	x-smpp-system-id	No default value	After restart
channel-any_name_for_sms	x-smpp-system-type	No default value	After restart
channel-any_name_for_sms	x-smpp-tls-certificate-file-password	No default value	After restart
channel-any_name_for_sms	x-smpp-tls-certificate-password	No default value	After restart
channel-any_name_for_sms	x-smpp-tls-mode	off	After restart
channel-any_name_for_sms	x-smpp-tls-path-to-certificate	No default value	After restart
channel-any_name_for_sms	x-smpp-tls-version	1.2	After restart
channel-any_name_for_sms	x-smpp-ucs2-enc-schema	UCS-2BE	After restart
channel-any_name_for_sms	x-smpp-use-msg-payload	false	After restart
channel-any_name_for_sms	x-smpp-validity-period	No default value	After restart
settings #To be merged with the settings section of DMS#	logging-filter-active	false	After restart
settings #To be merged with the settings section of DMS#	logging-filter-spec		After restart
Section	Option	Default	Changes Take Effect