



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

## Genesys Info Mart

log4j Section

# log4j Section

- [console-pattern-layout](#)
- [file-pattern-layout](#)
- [log-file-name](#)
- [log4j.appender.ConsoleLogger.Threshold-log-file-size](#)
- [logging-level](#)
- [max-backup-index](#)

Use this configuration section to specify the Genesys Info Mart ETL options for logging events to a local file and to STDOUT. These options are separate from, and independent of, the Genesys Central Logger options that you specify in the **[log] section**.

## console-pattern-layout

**Default Value:** %d{ISO8601} %-5p %-12t %m%n

**Valid Values:** Any valid pattern string

**Changes Take Effect:** Immediately

**Dependencies:** None

For information about this option, refer to the Apache logging site: <http://logging.apache.org/index.html>

## file-pattern-layout

**Default Value:** %d{ISO8601} %-5p %-12t %m%n

**Valid Values:** Any valid pattern string

**Changes Take Effect:** Immediately

**Dependencies:** None

For information about this option, refer to the Apache logging site: <http://logging.apache.org/index.html>

## log-file-name

**Default Value:** gim\_etl.log

**Valid Values:** filespec

**Changes Take Effect:** Immediately

**Dependencies:** None

Specifies the path and file name of the log file. If you do not specify a path, the log files will be

created in the installation directory.

## log4j.appender.ConsoleLogger.Threshold

**Default Value:** info

**Valid Values:** trace, debug, info, warn, error, all, off

**Changes Take Effect:** Immediately

**Dependencies:** None

For information about this option, refer to the Apache logging site: <http://logging.apache.org/index.html>

## logging-level

**Default Value:** info

**Valid Values:** debug, info, warn, error, none, all, off

**Changes Take Effect:** Immediately

**Dependencies:** None

Determines whether local logging is enabled, and specifies the minimum level of events to log. The DEBUG, INFO and WARN values correspond to the Genesys Management Layer DEBUG, TRACE, and STANDARD logging values, respectively.

In releases earlier than 8.1.3, the valid values were DEBUG, INFO, WARN, and NONE.

## max-backup-index

**Default Value:** 10

**Valid Values:** Any positive integer

**Changes Take Effect:** Immediately

**Dependencies:** None

Specifies the maximum number of backup log files that are kept in addition to the active log file.

## max-log-file-size

**Default Value:** 50MB

**Valid Values:** Any number, followed by a scale (KB for kilobytes, MB for megabytes, or GB for gigabytes)

**Changes Take Effect:** Immediately

**Dependencies:** None

Specifies the maximum size of the active log file before it is considered full and renamed as a backup file.