



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

# Workforce Management

Builder

5/7/2025

# Builder

Options for this component are contained in the following configuration sections:

- [auth](#)
- [Options](#)
- [Client](#)
- [Server](#)
- [Identity](#)
- [trace](#)
- [Log](#)

## Tip

In the summary table(s) below, type in the Search box to quickly find options, configuration sections, or other values, and/or click a column name to sort the table. Click an option name to link to a full description of the option. Be aware that the default and valid values are the values in effect with the latest release of the software and may have changed since the release you have; refer to the full description of the option to see information for earlier releases.

**Power users:** [Download a CSV file](#) containing default and valid values and descriptions.

The following options are configured at the application level (in other words, on the application object).

Section	Option	Default	Changes Take Effect
auth	<a href="#">provider</a>	wfm	After restart
Client	<a href="#">CfgServerRequestTimeout</a>	15	Immediately
Client	<a href="#">SOAPTimeout</a>	120	Immediately
Identity	<a href="#">ApplicationType</a>	WFMBuilder	Immediately
Log	<a href="#">all</a>	stdout	Immediately
Log	<a href="#">buffering</a>	false	Immediately
Log	<a href="#">debug</a>	" " (string)	Immediately
Log	<a href="#">expire</a>	false	Immediately
Log	<a href="#">keep-startup-file</a>	false	After restart
Log	<a href="#">messagefile</a>	wfmbuilder.lms	Immediately
Log	<a href="#">segment</a>	false	Immediately
Log	<a href="#">standard</a>	stdout	Immediately
Log	<a href="#">trace</a>	" " (string)	Immediately
Section	Option	Default	Changes Take Effect

Section	Option	Default	Changes Take Effect
Log	<code>verbose</code>	standard	Immediately
Log	<code>x-json-log</code>	"" (empty string)	After restart
Log	<code>x-json-log.archive</code>	No default value	After restart
Log	<code>x-json-log.compress</code>	No default value	After restart
Log	<code>x-json-log.flush</code>	true	After restart
Log	<code>x-json-log.MaxLogRecordSize</code>	-1	After restart
Log	<code>x-json-log.purgeAge</code>	"" (empty string)	After restart
Log	<code>x-json-log.purgeCount</code>	"" (empty string)	After restart
Log	<code>x-json-log.rotateOnOpen</code>	false	After restart
Log	<code>x-json-log.rotation</code>	no default value	After restart
Log	<code>x-json-log.times</code>	No default value	After restart
Log	<code>x-ScheduleBuilderProgressTrace</code>	false	Immediately
Log	<code>x-ScheduleBuilderTrace</code>	false	Immediately
Log	<code>x-ScheduleLogPath</code>	" " (string)	Immediately
Log	<code>x-ScheduleMaxLogs</code>	1000	Immediately
Log	<code>x-SwordTrace</code>	false	Immediately
Options	<code>EnableTOOverlap</code>	false	Immediately
Options	<code>LimitOpenHoursByRequirements</code>	false	Immediately
Options	<code>MaxSchedulingThreadPoolSize</code>	50	Immediately
Options	<code>MultiSiteActivitiesEnabled</code>	false	Immediately
Options	<code>NameOrder</code>	1	Immediately
Options	<code>PreserveMarkedTime</code>	false	Immediately
Options	<code>Special100ShiftCheck</code>	false	Immediately
Server	<code>management-port</code>	None	After restart
trace	<code>exporter-ostream-enable</code>	false	After restart
trace	<code>exporter.otlp_grpc.enable</code>	false	After restart
trace	<code>exporter.otlp_grpc.endpoint</code>	http://localhost:4317	After restart
trace	<code>exporter.otlp_grpc.ssl_credentials_cacert_as_string</code>		After restart
trace	<code>exporter.otlp_grpc.ssl_credentials_cacert_path</code>		After restart
trace	<code>exporter.otlp_grpc.timeout</code>	10s	After restart
trace	<code>exporter.otlp_grpc.use_ssl_credentials</code>	false	After restart
Section	Option	Default	Changes Take Effect