



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Configuration Layer Objects Reference Guide

CfgGVPCustomer

12/17/2025

Contents

- [1 CfgGVPCustomer](#)
 - [1.1 Description](#)
 - [1.2 Filter Keys](#)
 - [1.3 Attributes](#)
 - [1.4 See Also](#)

CfGVPCustomer

Description

A *GVP Customer* is a collection of GVP IVRProfiles.

Filter Keys

Filter Name	Type	Description
dbid	int	A unique identifier of a folder. If specified, Configuration Server will return information only about this folder.
name	string	Name of a GVP Customer. Shall be specified as a character string. If specified, Configuration Server will return information only about the GVP Customers with that name.
tenant_dbid	int	A unique identifier of a tenant. If specified, Configuration Server will return information only about the GVP Customers that belong to this tenant.
reseller_dbid	int	A unique identifier of a GVP Reseller. If specified, Configuration Server will return information only about the GVP Customers that belong to this GVP Reseller.
state	int	Current state of a GVP Customer (see type CfGObjectState). If specified, Configuration Server will return information only about GVP Customers that are currently in this state.

Attributes

- **DBID** — An identifier of this object in the Configuration Database. Generated by Configuration Server and is unique within an object type. Identifiers of deleted objects are not used again. Read-only.

- resellerDBID — A unique identifier of the [CfgGVPReseller](#) to which this GVP Customer is allocated. Mandatory. Once specified, cannot be changed
- tenantDBID — A unique identifier of the [CfgTenant](#) to which this GVP Customer is allocated. Populated from GVP Reseller. Read-only
- name — A pointer to name of the GVP Customer. Mandatory. Must be unique within the Configuration Database.
- displayName — A name for this GVP Customer that appears on the console display
- channel — The GVP channel used by this GVP Customer.
- notes — Optional notes and information relevant for this GVP Customer.
- isProvisioned — If this GVP Customer is provisioned in the switch database. Refer to [CfgFlag](#).
- isAdminCustomer — If this GVP Customer is classified as an Administrative Customer. Refer to [CfgFlag](#).
- timeZoneDBID — A [CfgTimeZone](#) associated with this GVP Customer
- state — Current object state. Mandatory. Refer to [CfgObjectState](#).
- userProperties — A pointer to the list of user-defined properties. Parameter userProperties has the following structure: Each key-value pair of the primary list (TKVList *userProperties) uses the key for the name of a user-defined section, and the value for a secondary list, that also has the TKVList structure and specifies the properties defined within that section.

See Also

[CfgDeltaGVPCustomer](#)

[CfgGVPIVRProfile](#)