

# **GENESYS**

This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

# Speech and Text Analytics

8.5.502.04

# 8.5.502.04

# Speech and Text Analytics Release Notes

Release Date	Release Type	Restrictions	AIX	Linux	Solaris	Windows
02/10/16	General					Χ

## Contents

- 18.5.502.04
  - 1.1 Helpful Links
  - 1.2 What's New
  - 1.3 Resolved Issues
  - 1.4 Upgrade Notes

#### What's New

This release includes only resolved issues.

#### Helpful Links

#### Releases Info

- List of 8.5.x Releases
- 8.5.x Known Issues

**Product Documentation** 

SpeechMiner

**Genesys Products** 

List of Release Notes

### **Important**

This version was first released as a Hot Fix on 02/09/16.

## Resolved Issues

This release contains the following resolved issues:

When working in an Analytics deployment, SpeechMiner can now correctly recognize silence time during English, Spanish and Turkish language interactions recorded in Stereo mode. (PRSM-15572)

As part of this correction, run the following SQL command after installing this release:

```
update nleparams set SEG_LEN=4000 update GenRecRecognizeCommandArgs set value='2000' where language=-1 and cmd='nnetLatgenArgv' and arg='--max-active' update GenRecRecognizeCommandArgs set value='5' where language=-1 and cmd='nnetLatgenArgv' and arg='--lattice-beam' INSERT INTO [dbo].[GenRecRecognizeCommandArgs] ([language], [cmd], [arg], [value]) VALUES (16, N'latticeToCtmConfArgv', N'--acoustic-scale', N'0.0909090909') INSERT INTO [dbo].[GenRecRecognizeCommandArgs] ([language], [cmd], [arg], [value]) VALUES (16, N'nnetLatgenArgv', N'--acoustic-scale', N'0.0909090909') UPDATE versionTbl SET version='8.5.502.95'
```

In order to use Arabic recognition in your system, please contact Genesys Customer Service. (PRSM-15398)

# Upgrade Notes

To upgrade to release 8.5.502, refer to the SpeechMiner 8.5.x Upgrade Guide.

## **Important**

When upgrading from a version preceding 8.5.502 to 8.5.502 or later, all interactions are re-indexed. During the re-index process, all SpeechMiner functionalities, except searching by term function as expected.