

# **GENESYS**

This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

# Genesys Voice Platform

**ICMC Section** 

# ICMC Section

- CancelResponseTimeoutMSec
- ConnectMsgTimeoutMSec
- DNISIndicator
- eccSessionIdVarName
- eccvariablelist

- enablePreRouting
- ICMInterface
- ICMUnavailableAction
- NewCallTimeoutMsec
- RunScriptResultTimeoutMsec
- SessionIdleTimeoutMSec
- TransferOnDialogFailure
- translation-routed-call
- TrunkGroupID

# CancelResponseTimeoutMSec

**Default Value: 2500** 

Valid Values:

Changes Take Effect: After restart

CTI Connector waits for the (CONNECT/RELEASE) response to CancelResponse message from ICM for the specified time. If no response is received with in the configured time then CTIConnector shall clear the call.

## ConnectMsgTimeoutMSec

**Default Value:** 3500

Valid Values:

Changes Take Effect: After restart

CTI Connector waits for the (CONNECT\_TO\_RESOURCE/CONNECT/RELEASE) response from ICM for the specified time. If no response is received with in the configured time then CTIConnector shall clear the call.

## **DNISIndicator**

**Default Value:** 

Valid Values: sid, 1, 2, 3, 4, 5, 6, 7, 8, 9, 10

Changes Take Effect: After restart

This parameter value indicates which field fron RUN\_SCRIPT\_REQ message should be used for fetching the DNIS value.

#### eccSessionIdVarName

Default Value: userSessionId

**Valid Values:** 

Changes Take Effect: At start/restart

CTI Connector shall take the SessionId and send it to ICM through this variable. Example: userECCVar1 The variable name configured here ("userECCVar1" in the example) should be specified in the ECC Variables list. If not, the SessionId will not be sent in the NEW\_CALL message. By default, it will be set to "userSessionId" and the SessionId will be sent through userSessionId. If it is empty, the SessionId will not be sent in the NEW CALL message.

#### eccvariablelist

**Default Value:** userSessionId:5000

Valid Values:

Changes Take Effect: At start/restart

CTI Connector shall take the configured list of ECC variable names and register it with ICM through initial REGISTER\_VARIABLES message. The ECC variable names along with their tag values should be separated by comma. The ECC variable may be specified without a tag, in which case, CTIC will generate a tag for it. Example: userECCVar1:5010,userECCVar2,userECCVar3:5011 Default value is userSessionId:5000

#### enablePreRouting

**Default Value:** false

**Valid Values:** 

Changes Take Effect: After restart

This parameter should be set to true when call is pre-routed to ICM (for Network VRU deployment type 2/3/7/8/). In this case the CTI Connector sends REQUEST\_INSTRUCTION message for establishing the call with ICM.

#### **ICMInterface**

**Default Value:** 0 **Valid Values:** 0, 1

Changes Take Effect: After restart

This parameter indicates about the interface that CTIC shall use to communicate with ICM. By default

CTIConnector shall use the Service Control Interface to communicate with ICM.

#### **ICMUnavailableAction**

**Default Value:** hangup

Valid Values: hangup, transfer

Changes Take Effect: At start/restart

This parameter describes action to take when the ICM connection break during a call . When action is 'transfer' CTIC transfers the call using REFER to the destination specified in the "cti.FailoverNumber" in IVR profile.

#### NewCallTimeoutMsec

**Default Value: 1500** 

**Valid Values:** 

Changes Take Effect: After restart

CTI Connector waits for the (RUN\_SCRIPT\_REQ/CONNECT/RELEASE) response to NEW\_CALL message from ICM for the specified time. If no response is received with in the configured time then CTIConnector shall clear the call.

## RunScriptResultTimeoutMsec

**Default Value:** 2500

**Valid Values:** 

Changes Take Effect: After restart

CTI Connector waits for the (RUN\_SCRIPT\_REQ/CONNECT/RELEASE) response to Run Script Result message from ICM for the specified time. If no response is received with in the configured time then CTIConnector shall clear the call.

#### SessionIdleTimeoutMSec

**Default Value: 120000** 

Valid Values:

Changes Take Effect: After restart

Maximum time the call will be kept active in CTIConnector, after the timeout CTIConnector will clear the call.

# TransferOnDialogFailure

**Default Value:** false **Valid Values:** 

Changes Take Effect: At start/restart

This parameter describes action to take when the ICM responds with DIALOGUE\_FAILURE\_EVENT for RUN\_SCRIPT\_RESULT. When it is set to 'true' CTIC transfers the call using REFER to the destination specified in the "cti.FailoverNumber" in IVR profile.

#### translation-routed-call

Default Value: false

Valid Values:

Changes Take Effect: After restart

This parameter value indicates CTIC whether the incoming is translation routed or normal call. The default value for this parameter is false. This should be set to true for Type 8 Network VRU deployment.

# TrunkGroupID

**Default Value:** 0 **Valid Values:** 

Changes Take Effect: After restart

The Trunk Group ID information is sent to ICM for every call through VRU-PG for ICM reporting purpose