

# **GENESYS**<sup>®</sup>

This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

### Universal Routing Reference

Support of HTTP Proxies

4/30/2025

## Support of HTTP Proxies

Starting with 8.1.400.27, URS provides support of HTTP Proxies for an "https://" type of request. HTTP Proxies are specified either in the request itself or globally at the URS Application level, in the web section.

Starting with 8.1.400.45, URS can use the HTTP CONNECT method to establish a secure tunnel between URS and the web server when accessing a secure web server through a proxy server. The option proxy\_use\_connect controls the connection method.

#### def\_https\_proxy\_host

Location in Configuration Layer by precedence: web section of URS Default Value: An empty string Valid Values: Any valid host name Changes Take Effect: After restart

This option specifies the HTTP Proxy host for an "https://" type of connection.

#### def\_https\_proxy\_port

Location in Configuration Layer by precedence: web section of URS Default Value: An empty string Valid Values: TCP port Changes Take Effect: After restart

This option specifies the HTTP Proxy port for an "https://" type of connection.

URS checks these options only if a request does not contain the HTTP Proxy host and port specified. HTTP Proxy for "https://" must be fully trusted and support secure connection on the Proxy port.

#### proxy\_use\_connect

Location in Configuration Layer by precedence: web section of URS Default Value: true Valid Values: true, false Changes Take Effect: After restart

This option specifies the connection method to a secure web server through a HTTP proxy server.

- A value of *true* uses the HTTP CONNECT method. URS communicates with web servers through HTTP proxy and performs TLS negotiations directly with the web server.
- A value of *false* uses the legacy method (not recommended). URS communicates with web servers through HTTP proxy and performs TLS negotiations with the proxy server.