



This PDF is generated from authoritative online content, and is provided for convenience only. This PDF cannot be used for legal purposes. For authoritative understanding of what is and is not supported, always use the online content. To copy code samples, always use the online content.

Log File Management Tool Deployment and User's Guide

Deployment of RSYNC on a Solaris host

Deployment of RSYNC on a Solaris host

This section describes how a Solaris application server host can be configured with RSYNC for LFMT collection.

Installation of RSYNC on Solaris

1. Download the following software packages from the website www.sunfreeware.com:
 - `libgcc-3.4.6-sol10-sparc-local.gz`
 - `popt-1.16-sol10-sparc-local.gz`
 - `libiconv-1.14-sol10-sparc-local.gz`
 - `libintl-3.4.0-sol10-sparc-local.gz`
 - `rsync-3.0.9-sol10-sparc-local.gz`
2. Copy each file to the `/usr/sfw/bin` directory on the Solaris host.
3. Unzip and install the file `libgcc-3.4.6-sol10-sparc-local.gz` from the `/usr/sfw/bin` directory, as follows:
 - a. Enter the following commands to unzip the file and start the installation:

```
gunzip libgcc-3.4.6-sol10-sparc-local.gz
pkgadd -G -d libgcc-3.4.6-sol10-sparc-local
```
 - b. When prompted for the packages to be processed, enter all or press Enter.
 - c. When prompted if you want to create the base directory, enter `y`.

When installation is complete, the following message appears:

```
Installation of <SMClgcc346> was successful.
```
4. Unzip and install the file `popt-1.16-sol10-sparc-local.gz` from the `/usr/sfw/bin` directory, as follows:
 - a. Enter the following commands to unzip the file and start the installation:

```
gunzip poprt-1.16-sol10-sparc-local.gz
pkgadd -G -d poprt-1.16-sol10-sparc-local
```
 - b. When prompted for the packages to be processed, enter all or press Enter.

When installation is complete, the following message appears:

```
Installation of <SMCpopt> was successful.
```
5. Unzip and install the file `libiconv-1.14-sol10-sparc-local.gz` from the `/usr/sfw/bin` directory, as follows:
 - a. Enter the following commands to unzip the file and start the installation:

```
gunzip libiconv-1.14-sol10-sparc-local.gz
pkgadd -G -d libiconv-1.14-sol10-sparc-local
```

- b. When prompted for the packages to be processed, enter all or press Enter.

When installation is complete, the following message appears:

```
Installation of <SMCliconv> was successful.
```

6. Unzip and install the file `libintl-3.4.0-sol10-sparc-local.gz` from the `/usr/sfw/bin` directory, as follows:

- a. Enter the following commands to unzip the file and start the installation:

```
gunzip libintl-3.4.0-sol10-sparc-local.gz
pkgadd -G -d libintl-3.4.0-sol10-sparc-local
```

- b. When prompted for the packages to be processed, enter all or press Enter.

When installation is complete, the following message appears:

```
Installation of <SMClintl> was successful.
```

7. Unzip and install the file `rsync-3.0.9-sol10-sparc-local.gz` from the `/usr/sfw/bin` directory, as follows:

- a. Enter the following commands to unzip the file and start the installation:

```
gunzip rsync-3.0.9-sol10-sparc-local.gz
pkgadd -G -d rsync-3.0.9-sol10-sparc-local
```

- b. When prompted for the packages to be processed, enter all or press Enter.

When installation is complete, the following message appears:

```
Installation of <SMCrsync> was successful.
```

8. Make sure that RSYNC is in the `/usr/bin` directory. To check, enter the command `which rsync`. You will get one of two responses:

- `/usr/bin/rsync`—RSYNC is in the correct directory.
- `<install directory/rsync>`—RSYNC is not in the correct directory; enter `cp <install directory/rsync> /usr/bin` to copy it to the correct directory.

9. Repeat this procedure, starting at step 2 for each Solaris host.